

ciforth manual

A close-to-ISO/computer-intelligence forth for the ARM.

This is a standard-ISO Forth (mostly, see the section portability) for the configuration called lina64:

- version 2023Mar30
- 64-bits protected mode
- running under Linux
- contains security words
- the full ISO CORE set is present, possibly after loading
- headers with source fields

Albert van der Horst

Dutch Forth Workshop

Copyright © 2000,2012 Dutch Forth Workshop

Permission is granted to copy with attribution. Program is protected by the GNU Public License.

1 Overview

Forth is an interactive programming system. ciforth is a family of Forth's that can be generated in many different version for many different operation systems. It is sufficiently close to the ISO standard to run most programs intended to be portable. It deviates where less used features where objectionable to implement. See Chapter 4 [Manual], page 7, Section Portability.

This file documents what you as a user needs to know for using this particular version of ciforth called "lina64" once it is installed on your system.

ciforth consists of three files:

- `lina64` : the program
- `ciforth.ps` `ciforth.html` : the documentation
- `forth.lab` : source library for auxiliary programs

These files are generated together by a generic system from the file `ciriscv.gnr` . The documentation applies to the ciforth with which it goes.

If your Forth doesn't fit the description below get a new version. The information below allows an expert to reconstruct how to generate a corresponding version. Not all of it may make sense to you. Tell him whether you want to fit the Forth to the description or vice versa (see Chapter 3 [Rationale & legalese], page 5).

These are the features:

All ciforth's are *case sensitive* . This is version 2023Mar30. It is running in protected mode. It is running under Linux Blocks are allocated in files. A number has a precision of 64 bits. It calls linux system from Forth directly. It has compiler security, sacrificing some ISO compatibility. It use PP instead of the ISO >IN It contains the full ISO CORE in the kernel, more than is needed to make it self contained. It contains a field in the header to point to source. It is indirect threaded.

If you are new to Forth you may want to read the Gentle Introduction, otherwise you better skip it. The third chapter most users will not be interested in.

2 Gentle introduction

A Forth system is a database of small programs. The database is called the dictionary. The programs are called *word* 's, or definitions. The explanation of words from the dictionary is called a glossary.

First of all, a Forth system is an environment that you enter by running it:

'lina64'

Like in a Disk Operating System a *word* is executed by typing its name, but unlike in a DOS several programs can be specified on the same line, interspersed with numbers. Also names can be anything, as long as they don't contain spaces.

A program may leave one or more results, and the next program can use it. The latest result is used up first, hence the name lifo buffer. (last in, first out).

For example:

```
albert@apple:~/forth/fig86 > lina64

ciforth beta $RCSfile: ci86.gnr,v $ $Revision: 6.122 $

1 2 + 7 *
OK
.
21 OK
```

1 2 and 7 are numbers and are just remembered as they are typed in. 'OK' and '21 OK' are the answer of the computer. + is a small program with an appropriate name. It adds the two numbers that were entered the latest, in this case 1 and 2. The result 3 remains, but 1 and 2 are consumed. Note that a name can be anything, as long as it doesn't contain spaces. The program * multiplies the 3 and the 7 and the result is 21. The program . prints this results. It could have been put on the same line equally easily.

You will be curious about what are all those commands available. Of course they are documented, but you can find the exact set by typing **WORDS** . Programs can be added to the database by special programs: the so called *defining word* 's. A defining word generally gets the name of the new word from the input line.

For example: a constant is just a program that leaves always the same value. A constant is created in this way, by the defining word **CONSTANT** :

```
127 CONSTANT MONKEY    12 .
12 OK
```

You can check that it has been added, by typing **WORDS** again.

The above must not be read like:

a number, two programs and again a number etc.... ,
but as:

a number, a program and a name that is consumed,
and after that life goes on. The '12 .' we put there for demonstration purposes, to show that **CONSTANT** reads ahead only one word. On this single line we do two things, defining 'MONKEY' and printing the number 12. We see that **CONSTANT** like any other program consumes some data, in this case the 127 that serves as an initial value for the constant called 'MONKEY' .

You may get 'constant ? ciforth ERROR # 12 : NOT RECOGNIZED '. That is because you didn't type in what I said. lina64 is case sensitive. If you want to change that consult the section "Common problems". (see Chapter 6 [Errors], page 29).

A very important defining word is `:`, with its closure `;`.

```
: TEST 1 2 + 7 * ;      21 .
21 OK
```

In this case not only the name ‘TEST’ is consumed, but none of the remaining numbers and programs are executed, up till the semicolon `;`. Instead they form a specification of what ‘TEST’ must do. This state, where Forth is building up a definition, is called *compilation mode*. After the semicolon life continues as usual. Note that `;` is a program in itself too. But it doesn’t become part of TEST. Instead it is executed immediately. It does little more than turning off compilation mode.

```
TEST TEST + .
42 OK
: TEST+1 TEST 1 + . ; TEST+1
22 OK
```

We see that ‘TEST’ behaves as a shorthand for the line up till the semi colon, and that in its turn it can be used as a building block.

The colon allows the Forth programmer to add new programs easily and test them easily, by typing them at the keyboard. It is considered bad style if a program is longer than a couple of lines. Indeed the inventor of Forth Chuck Moore has written splendid applications with an average program length of about one line. Cathedrals were built by laying stone upon stone, never carved out of one rock.

The implementation of the language Forth you look at is old fashioned, but simple. You as a user have to deal with only three parts/files : this documentation, the executable program, and the library file, a heap of small programs in source form. There may be several documentation files, but they contain the same information in a different format.

There is an ISO standard for Forth and this Forth doesn’t fully comply to it. Still by restricting yourself to the definitions marked as ISO in the glossary, it is quite possible to write an application that will run on any ISO-compliant system.

Because of the way Forth remembers numbers you can always interrupt your work and continue. For example

```
: TEST-AGAIN
1 2 + [ 3 4 * . ]
12 OK
7 * ;
OK
```

What happened here is that some one asked you to calculate “3 times 4” while you were busy with our test example. No sweat! You switch from compilation mode to normal (interpret) mode by `[`, and back by `]`. In the meantime, as long as you don’t leave numbers behind, you can do anything. (This doesn’t apply to adding definitions, as you are in the process of adding one already.)

3 Rationale & legalese

3.1 Legalese

This application currently is copyright by Albert van der Horst. This Forth is called ciforth and is made available by the D.F.W.. All publications of the D.F.W. are available under GPL 2, the GNU public license. The file `COPYING` containing the legal expression of these lines must accompany it.

You can make closed source program with the -c options. Such programs are naturally your own, quite the same as programs build with the gcc compiler. However also if you base an application program on ciforth, you need not make its source available, even if the application contains the Forth interpreter exposed. This would be a derived work and, in a strict interpretation of the GPL, such interpretive systems based on ciforth are always legally obliged to make the source available. Because Forth is “programming by extending the language”, we consider this “normal use in the Forth sense” as expressed by the following statement.

In addition to the GPL Albert van der Horst grants the following rights in writing:

The GPL is interpreted in the sense that a system based on ciforth and intended to serve a particular purpose, that purpose not being a “general purpose Forth system”, is considered normal use of the compilation system, even if it could accomplish everything ciforth could, under the condition that the ciforth it is based on is available in accordance to the GPL rules, and this is made known to the user of the derived system.

So if you base an application program on ciforth, you need not make its source available, even if it would be a derived system in a strict interpretation of the GPL.

3.2 Rationale

This Forth is meant to be simple. What you find here is a Forth for the Aarch 64 . You need just the executable to work. You choose the format you prefer for the documentation. They all have the same content. You can use the example file with blocks, you have the assembler source for your Forth, but you can ignore both.

3.3 Source

In practice the GPL means (: this is an explanation and has no legal value!)

They may be further reproduced and distributed subject to the following conditions:

The three files comprising it must be kept together and in particular the reference section with the World Wide Web sites.

The latest version of lina64 is found at

`'http://home.hccnet.nl/a.w.m.van.der.horst/ciforth.html'`.

Via that link you can also download ciforth's for other OS's and the generic system, if you want to make important modifications. Also you can see how you can contact the author. Otherwise in case of questions about this ciforth, contact the person or organisation that generated it for you.

This Forth builds on fig-Forth. It is based on the work of Charlie Krajewski and Thomas Newman, Hayward, Ca. still available via taygeta. The acknowledgments for systems that serves as a base, in particular the original fig-Forth, are found in the generic documentation, including detailed information how these systems can be obtained.

Important:

If you just want to use a Forth, you most certainly do not want the generic system. Great effort is expended in making sure that this manual contains all that you need, and nothing that

might confuse you. The generic system on the contrary contains lots that you don't need, and is confusing as hell.

If you are interested in subjects like history of Forth, the rationale behind the design and such you might want to read the manual for the generic Forth.

3.4 The Generic System this Forth is based on.

The source and executable of this ciforth was generated, out of at least dozens of possibilities, by a generic system. You can configure the operating system, memory sizes, file names and minor issues like security policy. You can select between a 16, 32 and 64 bit word size. You may undertake more fundamental changes by adapting one or more of the macro header files. An important goal was to generate exactly fitting documentation, that contains only relevant information and with some care your configuration will have that too. This generic system can be obtained via '<http://home.hccnet.nl/a.w.m.van.der.horst/ciforth.html>'. '

4 Manual

4.1 Getting started

4.1.1 Hello world!

Type `'lina64'` to get into your interactive Forth system. You will see a signon message. While sitting in your interactive Forth doing a “hello world” is easy:

```
"Hello world!" TYPE
Hello world! OK
```

Note that the computer ends its output with `'OK'` to indicate that it has completed the command.

Making it into an interactively usable program is also easy:

```
: HELLO "Hello world!" TYPE CR ;
OK
HELLO
Hello world!
OK
```

This means you type the command `'HELLO'` while you are in `lina64`. As soon as you leave `lina64`, the new command is gone.

If you want to use the program a second time, you can put it in a file `hello.frt`. It just contains the definition we typed earlier:

```
: HELLO "Hello world!" TYPE CR ;
```

This file can be INCLUDED in order to add the command `'HELLO'` to your Forth environment, like so:

```
"hello.frt" INCLUDED
OK
HELLO
Hello world!
OK
```

During development you probably have started with `'lina64 -e'`, so you need just type

```
INCLUDE hello.frt
```

In order to make a stand alone program to say hello you can use that same source file, again `hello.frt`. Now build the program by
`lina64 -c hello.frt`

(That is `c` for compile.) The result is a file `hello`. This file can be run from your command interpreter, or shell. It then will execute the last word defined in the source file in this case `'HELLO'`. It is a single file that you can pass to some one else to run on their computer, without the need for them to install Forth. For the compiler to run you must have the library correctly installed.

If that failed, or anything else fails, you will get a message with at least `'ciforth ERROR ###'` and hopefully some more or less helpful text as well. The `'###'` is an error number. See Chapter 6 [Errors], page 29, Section Explanations.

Note for the old hands. Indeed the quoted strings are not ISO. They surely are a Forth-like extension. Read up on denotations, and the definition of " .

In lina64 you never have to worry about the life time of those quoted strings, they are allocated in the dictionary and are permanent.

4.1.2 The library.

If you want to run a program written on some other Forth, it may use facilities that are not available in lina64's kernel, but they may be available in the *library* . A library is a store with facilities, available on demand. Forth as such doesn't have a library mechanism, but lina64 does.

lina64 uses the *blocks* as a library by addition of the word **WANTED** and a convention. Starting with '**lina64 -w**' or most any option you have this facility available. If you are already in lina64, you can type '**1 LOAD**'. The extension of '**.lab**' in **forth.lab** means Library Addressable by Block.

Now we will add **DO-DEBUG** using this library mechanism. It is used immediately. It is handy during development, after every line it shows you what numbers Forth remembers for you. Also from now on the header of each block that is **LOAD** -ed is shown.

Type ('**1 LOAD**' may not be necessary):

```
1 LOAD
"DO-DEBUG" WANTED
OK
DO-DEBUG
```

```
S[ ] OK 1 2
```

```
S[ 1 2 ] OK
```

(You can turn **DO-DEBUG** off with **NO-DEBUG .**)

More convenient than **WANTED** is **WANT** that adds all words that are on the remainder of the line, so without quotes.

If you try to **INCLUDE** a program, you may get errors like '**TUCK? ciforth ERROR # 12 : NOT RECOGNIZED**'. See Chapter 6 [Errors], page 29, Section Explanations. Apparently, lina64 doesn't know about a forth word named **TUCK** , but after '**"TUCK" WANTED**' maybe it does. You may try again.

The convention about the way the library file must be organized for **WANTED** to find something is simple. It is divided into blocks of 16 lines. The first line is the header of the block. If the word we are looking for is mentioned in the header, that block is compiled. This continues until the word has been defined, or the end of the search area is reached. This is marked by a screen with an empty index line. I tell you this not because you need to know, but to show that there is nothing to it.

The library file contains examples for you to load using **WANT** . Try

```
WANT SIEVE
LIM # 4 ISN'T UNIQUE
OK
10 SIEVE
KEY FOR NEXT SCREEN
ERATOSTHENES SIEVE -- PRIMES LESS THAN 10 000
0 002 003 ...
(lots of prime numbers.)
```

4.1.3 Development.

If you want to try things out, or write a program – as opposed to just running a ready made program – you best start up lina64 by ‘lina64 -e’. That is **e** for elective. ‘lina64 -e’ instructs lina64 to load screen 5 (**e** is the 5-th letter.)

You can configure this screen 5 to suit your particular needs, by just using some programmers editor. We will come back to that later.

You will have available:

1. **WANTED** and **WANT .** ‘WANT xxx yyy’ is equivalent to “xxx" WANTED "yyy" WANTED’ , but it is more convenient.
2. **DH. H. B. DUMP FARDUMP**
For showing numbers in hex and parts of memory.
3. **SEE**
To analyse words, showing the source code of compiled words. (Also known as **CRACK .**)
4. **LOCATE**
To show the part of the source file where the word is defined, or, if loaded from the library file, the block where it is defined.
5. **OS-IMPORT**
To be able to type shell-commands from within Forth as if you were in a terminal window.
...

Because this ciforth is “hosted”, meaning that it is started from an operating system, you can develop in a convenient way. Start lina64 in a window, and use a separate window to start your editor. Try out things in lina64. If they work, paste the code into your editor. If a word works, but its source has scrolled off the screen, you can recover the source using **SEE .** If you have constructed a part or all of your program, you can save it from your editor to a file. Then by the command ‘**INCLUDE <file-name>**’ load the program in lina64 and do some further testing.

You are not obliged to work with separate windows. Suppose your favorite editor is called **vi**. After

```
"vi" OS-IMPORT vi
```

you can start editing a file in the same way as from the shell. Of course you now have to switch between editing a file and lina64. But at least you need not set up your Forth again, until your testing causes your Forth to crash.

4.1.4 Finding things out.

If you want to find things out you must start up lina64 again by ‘lina64 -e’. The sequence

```
WANT TUCK
LOCATE TUCK
```

shows you the source for TUCK if it is in the library somewhere.

```
WANT TUCK
SEE TUCK
```

show you the source for TUCK if it is in the library or in the kernel, but without comment or usage information.

4.2 Configuring

For configuring your lina64, you may use "newforth" **SAVE-SYSTEM** . This will do most of the time, but then you build in the **SAVE-SYSTEM** command as well. For configuring your lina64, without enlarging the dictionary, you may use the following sequence

```
S" myforth.lab" BLOCK-FILE $! \ Or any configuration command
1 LOAD
WANT SAVE-SYSTEM
: DOIT
  '_pad 'FORTH FORGET-VOC
  '_pad >NFA @ DP !
  "newforth" SAVE-SYSTEM BYE ;
DOIT
```

Here 'DOIT' trims the dictionary just before saving your system into a file. `_pad` is the first word of the facilities in screen 1 that was loaded. (This was different in previous version of ciforth.)

FAR-DP allows to have a disposable part of the dictionary. If you decide to use this facility for your own purposes, make sure to always **FORGET** the disposed off words. The `'-c'` option uses this to avoid having source files as part of an executable image.

4.3 Concepts

A forth user is well aware of how the memory of his computer is organised. He allocates it for certain purposes, and frees it again at will.

The last-in first-out buffer that remembers data for us is called the *data stack* or sometimes *computation stack* . There are other stacks around, but if there is no confusion it is often called just the *stack* . Every stack is in fact a buffer and needs also a *stack pointer* to keep track of how far it has been filled. It is just the address where the last data item has been stored in the buffer.

The *dictionary* is the part of the memory where the *word's* are (see Section 8.6 [DICTIONARY], page 57). Each word owns a part of the dictionary, starting with its name and ending where the name of the next word starts. This structure is called a *dictionary entry* . Its address is called a *dictionary entry address* or *DEA* . In ciforth's this address is used for external reference in a consistent way. For example it is used as the *execution token* of a word in the ISO sense. In building a word the boundary between the dictionary and the free space shifts up. This process is called *allocating* , and the boundary is marked by a *dictionary pointer* called `DP` . A word can be executed by typing its name. Each word in the dictionary belongs to precisely one *word list* , or as we will say here namespace. Apart from the name, a word contains data and executable code, (interpreted or not) and linking information (see Section 8.4.7 [NAMESPACE], page 53). The order of words in a wordlist is important for looking them up. The most recent words are found first.

The concept word list is part of the ISO standard, but we will use *namespace* . A namespace is much more convenient, being a word list with a name, created by **NAMESPACE** . ISO merely knows *word list identifier* 's, a kind of handle, abbreviated as *WID* . A new word list is created by the use of **NAMESPACE** . When looking up a word, only the wordlists that are in the current *search order* are found. By executing the namespace word the associated word list is pushed to the front of the search order. In fact in ciforth's every DEA can serve as a WID. It defines a wordlist consisting of itself and all earlier words in the same namespace. You can derive the WID from the DEA of a namespace by `>WID` .

A word that is defined using `:` is often called a *colon definition*. Its code is called *high level* code.

A high level word, one defined by `:`, is little more than a sequence of addresses of other words. The *inner interpreter* takes care to execute these words in order. It acts by fetching the address pointed by 'HIP', storing this value in register 'WOR'. It then jumps to the address pointed to by the address pointed to by 'WOR'. 'WOR' points to the code field of a definition which (at offset `forthdef(>CFA)`) contains the address of the code which executes for that definition. For speed reasons this offset is chosen to be zero. This usage of indirect threaded code is a major contributor to the power, portability, and extensibility of Forth.

If the inner interpreter must execute another high level word, while it is interpreting, it must remember the old value of 'HIP', and this so called *nesting* can go several levels deep. Keeping this on the data stack would interfere with the data the words are expecting, so they are kept on a separate stack, the *return stack*. Apart from 'HIP' and 'WOR' the return and data stack are kept in registers named 'RPO' and 'SPO'. If you're interested in the actual registers, you can inspect the assembler source file that goes with this Forth. The usage of two stacks is another hall mark of Forth.

A word that generates a new entry in the dictionary is called a *defining word* (see Section 8.4 [DEFINING], page 51). The new word is created in the `CURRENT` word list.

Each processor has a natural size for the information. (This is sometimes called a machine word). For a Pentium processor this is 32 or 64 bit, for the older Intel 8086 it is 16 bit. The pendant in Forth is called a *cell* and its size may deviate from the processor you are running on. For this cforth it is 64. It applies to the data remembered in the data stack, the return addresses on the return stack, memory accesses `@` and `!`, the size of `VARIABLE`'s and `CONSTANT`'s. In Forth a cell has no hair. It is interpreted by you as a signed integer, a bit-map, a memory address or an unsigned number. The operator `+` can be used to add numbers, to set a bit in a bitmap or advance a pointer a couple of bytes. In accordance with this there are no errors such as overflow given.

Sometimes we use data of two cells, a *double*. The high-order cell is most accessible on the stack and if stored in memory, it is lowest.

The code for a high level word can be typed in from the terminal, but it can also be fed into Forth by redirection from a file, `INCLUDED` from a file or you can *load* it from the file `forth.lab`, because you can load a piece of this library at will once you know the block number. This file is divided into *blocks* of 1 Kbyte. They may contain any data, but a most important application is containing source code. A block containing source code is called a *screen*. It consists of 16 lines of 64 characters. In cforth the 64-th character is `^J` such that they may be edited in a normal way with some editors. To *load* such a screen has the same effect as typing its content from the terminal. The extension `lab` stands for *Library Addressable by Block*,

Traditionally Forthers have things called *number*'s, words that are present in the source but are interpreted or compiled, and are thought of not as being executed but rather being a description of something to be put on the stack directly. In early implementations the word 'NUMBER' was a catch-all for anything not found in the dictionary, and could be adapted to the application. For such an extensible language as Forth, and in particular where strings and floating point numbers play an increasing role, numbers must be generalised to the concept of *denotation*'s. The need for a way to catch those is as present as it was in those early days. Denotations put a constant object on the stack without the need to define it first. Naturally they look, and in fact are, the same in both modes. Here we adopt a practice of selecting a type of the denotations based on the first letters, using `PREFIX`. This is quite practical and familiar. Examples of this are (some from C, some from assemblers, some from this Forth) :

```

'a'
^A
ODEAD
$8000403A
0x8000403A
#3487
0177
S" Arpeggio"
"JAMES BROWN IS DEAD"
" JK "
'DROP
' DROP

```

These examples demonstrate that a denotation may contain spaces, and still are easy to scan. And yes, I insist that ‘ ’ DROP’ is a denotation. But ‘ ’DROP’ is clearer, because it can only be interpreted as such; it is not a valid word.

Of course a sensible programmer will not define a word that looks like a denotation :

```
: 7 CR "This must be my lucky day" TYPE ; ( DON'T DO THIS)
```

4.4 Portability

If you build your words from the words defined in the ISO standard, and are otherwise careful, your programs may run on other systems that are ISO standard.

There are no gratuitous deviations from the standard, but a few things are not quite conforming.

1. The error system uses **CATCH** and **THROW** in a conforming way. However the codes are not assigned according to the table in the standard. Instead positive numbers are ciforth errors and documented in this manual. ciforth's errors identify a problem more precisely than the standard admits. An error condition that is not detected has no number assigned to it. Negative numbers are identical to the numbers used by the host operating system. No attempt is made to do better than reproduce the messages belonging to the number as given by **strerror**.
2. As **ABORT** **ABORT QUIT** are not implemented using **THROW** it is not possible to catch those words.
3. There is no **REFILL** . This is a matter of philosophy in the background. You may not notice it.
Consequences are that **BLK** is not inspected for every word interpreted, but that blocks in use are locked. Files are not read line by line, but read in full and evaluated.
4. It uses **PP** instead of the ISO **>IN**
The **>IN** that is available via the library is a fake, that can only be read, but changing it has no effect. **PP** can be manipulated to have such effects as the familiar **0 >IN !** idiom.
5. Counting in **do** loops do not wrap through the boundary between negative and positive numbers. This is not useful on Forths of 32 bits and higher; for compatibility among ciforths 16 bit ciforths don't wrap either.
6. Namespaces are wordlists with a name. They push the wordlist to the search order, instead of replacing the topmost one, as is done by **VOCABULARY** (not an ISO-word) that is present in some other Forth's. In this sense **FORTH** and **ASSEMBLER** words are not conforming.
7. This is not strictly non-conforming, but worth mentioning here. In fact **lina64** contains only one state-smart word besides **LITERAL** (that word is **."**). All denotations are state-smart only because they use **LITERAL**

and the result is correct ISO behaviour for numbers. Knowledge of this is used freely in the libraries of ciforth; it is the right of a system developer to do so. The library is not a supposedly ISO-conforming program. It tends to rely on ciforth-specific and lina64-specific – but hopefully documented – behaviour. Understanding it requires some study of non-portable facilities.

8. When a file is INCLUDED it is read in as a whole, so there is never a need for REFILL . After WANT REFILL a REFILL is loaded that sets the parse pointer to the start of the next line. In nearly all cases this will accomplish the effect described by the standard.

Here we will explain how you must read the glossary of lina64, in relation to terminology in the ISO standard.

Whenever the glossary specifies under which conditions a word may *crash* , then you will see the euphemism *ambiguous condition* in the ISO standard.

For example:

Using HOLD other than between <# and #> leads to a crash.

Whenever we explicitly mention ciforth in a sentence that appears in a glossary entry, the behaviour may not apply to other ISO standard systems. This is called *ciforth specific behaviour* . If it mentions “this ciforth” or “lina64”, you cannot even trust that behaviour to be the same on other ciforth systems. Often this is called an “implementation defined” behaviour in the standard. A typical example is the size of a cell. Indeed we are obliged to specify this behaviour in our glossary, or we don’t comply to the standard. The behaviour of the other system may very well be a crash. In that case the standard probably declares this an “ambiguous condition”.

For example:

On this ciforth OUT is set to zero whenever CR is executed.

The bottom line is that you never want to write code where lina64 may crash. And that if you want your code to run on some other system, you do not want to rely on *ciforth specific behaviour* . If you couldn’t get around that, you must keep the specific code separate. That part has to be checked carefully against the documentation of any other system, where you want your code to run on.

By using CELL+ it is easy to keep your code 16/32/64 bit clean. This means that it runs on 16, 32 and 64 bits systems.

4.5 Compatibility with lina64 4.0.x

Since version 5.x changes have been made to increase compatibility with existing practice. By invoking WANT -legacy- you load a screen that forces compatibility with 4.x.x versions. You will notice that existing programs either invoke this, or have been reworked to not need legacy items. In either case, those programs have been tested with version 5.x

What the legacy items are can be seen from the screen that has -legacy- in its index line. In particular REQUIRE REQUIRED PRESENT? VOCABULARY WORD FIND (WORD) (PARSE) SAVE-INPUT RESTORE-INPUT WORD FIND (WORD) (PARSE) SAVE-INPUT RESTORE-INPUT are to be found in those screens. Note that by using legacy items your code may be in conflict with upcoming standards.

The names VOCABULARY and REQUIRE are being proposed for standardisation. The ciforth definitions with these names were not compatible with this proposal. So the REQUIRE of older versions is now called WANT . Likewise REQUIRED is renamed to WANTED . VOCABULARY is renamed to NAMESPACE , with the difference that NAMESPACE is not immediate. This allows to include the new standardised definitions in a loadable screen.

4.6 Saving a new system

We have said it before: “Programming Forth is extending the Forth language.”. A facility to save your system after it has been extended is essential. It can be argued that if you don’t have that, you ain’t have no Forth. It is used for two purposes, that are in fact the same. Make a customised Forth, like **you** want to have it. Make a customised environment, like a customer wants to have it. Such a “customised environment”, for example a game, is often called a *turnkey system* in Forth parlance. It hides the normal working of the underlying Forth.

In fact this is what in other languages would be called “just compiling”, but compiling in Forth means adding definitions to an interactive Forth. In ciforth “just compiling” is as easy as in any language (see Chapter 4 [Manual], page 7, Hello world!). Of course, whether you have a hosted system like this one `_HOSTED_MSDOS_` (like this one) or a booted system, it is clear that some system-dependant information goes into accomplishing this.

This has all been sorted out for you. Just use `SAVE-SYSTEM`. This accepts a string, the name you want the program-file to have. Having a program to execute a certain word is even easier, just use the `-c` option. See Chapter 4 [Manual], page 7, Section Libraries and options.

In the following it is explained. We use the naming convention of ISO about cells. A cell is the fundamental unit of storage for the Forth engine. Here it is 64 bits (8 bytes).

The change of the boot-up parameters at `+ORIGIN`, in combination with storing an image on disk goes a long way to extending the system. This proceeds as follows:

1. All user variables are saved by copying them from `'U0 @` to `'0 +ORIGIN`. The user variable `U0` points to the start of the user area. The length of the area is `0x40` cells. If in doubt check out the variable `'US` in the assembler code.
2. If all user variables are to be initialised to what they are in this live system skip the next step.
3. Adjust any variables to what you want them to be in the saved system in the `+ORIGIN` area. The initialisation for user variable `'Q` can be found at `' Q >DFA @ +ORIGIN`.
4. Adjust version information (if needed)
5. Copy your `lina64` to a new file using `PUT-FILE`. The difficult part is to add to the system specific header information about the new size, which is now from `BM` to `HERE`. The command `'WANT SAVE-SYSTEM` loads a version that does that correctly for your hosted system.

4.7 Memory organization

A running ciforth has 3 distinct memory areas.

They occur sequentially from low memory to high.

- The dictionary
- Free memory, available for dictionary, from below, and stacks, from above
- Stacks and the input buffer for the console and disk block buffers.

The lowest part of the free memory is used as a scratch area: `PAD`.

The dictionary area is the only part that is initialised, the other parts are just allocated.

The program as residing on disk must contain the first area. In addition it contains a header, to tell the Linux how to transfer the program to memory. Logically the Forth system consists of these 7 parts.

- Boot-up parameters
- Machine code definitions
- Installation dependant code

- High level standard definitions
- High level user definitions
- System tools (optional)
- RAM memory workspace

4.7.1 Boot-up Parameters

The boot-up area contains initial values for the registers needed for the Forth engine, like stack pointers, the pointers to the special memory area's, and the very important dictionary pointer DP that determines the boundary between the dictionary and free space.

They are copied to a separate area the *user area*, each time Forth is started. The bootup area itself is not changed, but the variables in the user area are. By having several user area's, and switching between them, ciforth supports multitasking. When you have made extensions to your system, like for instance you have loaded an editor, you can make these permanent by updating the initial values in the boot-area and saving the result to disk as an executable program. The boot-up parameters extend from '0 +ORIGIN' and supply an initial value for all of the user area. This is the image for the *user area*.

In ciforth the bootup parameters are more or less the data area belonging to the +ORIGIN word. Executing '0 +ORIGIN' leaves a pointer in this area.

4.7.2 Installation Dependent Code

KEY EMIT KEY? TYPE

CR BLOCK-READ and BLOCK-WRITE

are indeed different for different I/O models. This is of little concern to you as a user, because these are perfectly normal dictionary entries and the different implementations serves to make them behave similarly. There will however be more differences between the different configurations for ciforth for these words than habitually. These definitions are often revectorred especially those for output. Output is revectorred using TYPE. In other Forth's this is mostly done via KEY and CR separately. Input revectoring cannot be done via KEY. Redirection works and is easier most of the time.

4.7.3 Machine Code Definitions

The machine executable code definitions play an important role because they convert your computer into a standard Forth stack computer. It is clear that although you can define words by other words, you will hit a lowest level. The *code word*'s as these lowest level programs are called, execute machine code directly, if you invoke them from the terminal or from some other definition. The other definitions, called *high level* code, ultimately execute a sequence of the machine executable code words. The Forth *inner interpreter* takes care that these code words are executed in turn.

In the assembler source (if you care to look at it) you will see that they are interspersed with the high level Forth definitions. In fact it is quite common to decide to rewrite a code definition in high level Forth, or the other way around. The *Library Addressable by Block* contains an assembler, to add code definitions that will blend in like they were written in the kernel. Such definitions are to be closely matched with your particular ciforth, and you must be aware which registers play which role in ciforth. This is documented in the assembler source of this ciforth that accompanies this distribution. Of course it is also a rich source of examples how to make assembler definitions.

It bears repeating: code words are perfectly normal dictionary entries.

Note: if you want to change this ciforth's assembler source to fit your needs, follow the instructions present in the source, assembling as well as linking instructions.

4.7.4 High-level Standard Definitions

The high level standard definitions add all the colon-definitions, user variables, constants, and variables that must be available in a "Forth stack computer" according to the ISO standard. They comprise the bulk of the system, enabling you to execute and compile from the terminal, execute and *load* code from disk to add definitions etc. Changes here may result in deviations from the standard, so you probably want to leave this area alone. The technique described for the next section, forget and recompile, is not always possible here because of circular references. That is in fact no problem with an assembler listing, but it is if you load Forth code.

Again standard definitions words are perfectly normal dictionary entries.

4.7.5 User definitions

The user definitions contain primarily definitions involving user interaction: compiling aids, finding, forgetting, listing, and number formatting. Some of these are fixed by the ISO standard too. In ciforth most of those facilities are not available in the kernel, but from the library. This applies even to the ISO standard words from the 'TOOLS' wordset like **DUMP** (show a memory area as numbers and text) and **.S** (show the data stack). You can **FORGET** part of the high-level and re-compile altered definitions from disc. Mostly this is a mistake, and to make sure you mean it, you must change **FENCE** to defeat a protection mechanism.

A number of entries that could easily be made loadable are integrated in the assembler source of this ciforth version. Instead of forgetting them, you can load your own version on top of the existing system and waste some space.

Again user definitions words are perfectly normal dictionary entries.

4.7.6 System Tools

The boundary between categories are vague. A system tools is contrary to a user tool, a larger set of cooperating words. A text editor and machine code assembler are the first tools normally available. In ciforth those facilities are mostly not available in the kernel, but from the library. For example, an assembler is not part of the kernel as delivered, but it is available after 'WANT ASSEMBLERi86'. Beware! The assembler can only be loaded on top of a **CASE-SENSITIVE** system.

You can load a more elaborate assembler. See Chapter 5 [Assembler], page 25, Section Overview. They are among the first candidates to be integrated into your system by **SAVE-SYSTEM**.

An editor is not part of ciforth as delivered. Development in Linux uses the there available editors. Even without tools, code can be tested by piping it into Forth, then commanding Forth to look to the console, as follows :

```
' (echo 1 LOAD; cat pascal.frt - ) | lina64 '
```

Primitive and preliminary as this may seem, it has been used for quite substantial developments like the 80386 assembler.

More advanced is using Your Favorite Editor, followed by including files:

```
' "vim mysrc.frt" SYSTEM '
```

```
' "mysrc.frt" INCLUDED '
```

See Chapter 4 [Manual], page 7, Section Getting Started.

In an installed system you will put 'WANT OS-IMPORT WANT INCLUDE' in your electives screen (5), and just type 'vim mysrc.frt' to edit a file, without leaving lina64 and load it with 'INCLUDE mysrc.frt'

A Pentium 32 and a 8086 i86 Forth assembler are available in **forth.lab**. It must in due course be replaced by an ARM assembler. Screens are loaded in accordance with the system that is run, in other words an ARM system will simply refuse to load this assembler. The registers used by lina64 are called HIP, SPO, RPO and WOR. The mapping on actual processor registers is documented in the source.

It is essential that you regard lina64 as just a way to get started with Forth. Forth is an extensible language, and you can set it to your hand. But that also means that you must not hesitate to throw away parts of the system you don't like, and rebuilt them even in conflict with standards. Additions and changes must be planned and tested at the usual Forth high level. Some words critical for speed you can later rewrite as code words. Some words are easier to write in code right away.

Again words belonging to tools are perfectly normal dictionary entries.

4.7.7 RAM Workspace

The RAM workspace contains the compilation space for the dictionary, disc buffers, the computation and return stacks, the user area, and the console input buffer, From the fig-Forth user manual

For a single user system, at least 2k bytes must be available above the compiled system (the dictionary). A 16k byte total system is most typical.

It is indeed possible to do useful work, like factoring numbers of a few hundred digits, in a workspace of 2k bytes. More typical a workspace is several megabytes to over hundred megabytes.

32 and 64 bits system are set at 64Mbyte but this is arbitrary and could be set much higher or lower without consequences for system load or whatever. Before long we will put the dictionary space on 32-bits Linux to 4G minus something and forget about this issue forever.

The boundary between this area and the previous ones is pretty sharp, it is where DP points. The other areas are more of a logical distinction. But even this boundary constantly changes as you add and forget definitions. Multi-tasking requires allocation of extra areas. See Chapter 4 [Manual], page 7, Section Details of memory layout.

4.8 Specific layouts

4.8.1 The layout of a dictionary entry

We will divide the dictionary in entries. A *dictionary entry* is a part of the dictionary that belongs to a specific word. A *dictionary entry address* , abbreviated *DEA* is a pointer to the header of a dictionary entry. In ciforth a header extends from the lowest address of the entry, where the code field is, to the *past header address* , just after the last field address. A *dictionary entry* apart from the header owns a part of the dictionary space that can extend before the header (mostly the name of the entry) and after it (mostly data and code).

A dictionary entry has fields, and the addresses of fields directly offset from the dictionary entry address, are called *field address* . This is a bit strange terminology, but it makes a distinction between those addresses and other addresses. For example, this allows to make the distinction between a *data field address* , that is always present, and a *data field* in the ISO sense that has only a (differing) meaning for **CREATE DOES>** definitions. Typically, a field address contains a pointer. A *data field address* contains a pointer to near the *data field* , whenever the latter exists.

They go from lowest in memory to highest:

1. The code field. This is one cell. A pointer to such a field is called a *code field address* . It contains the address of the code to be executed for this word.
2. The data field, of the DEA, not in the ISO sense. This is one cell. A pointer to such a field is called a *data field address* . It contains a pointer to an area owned by this definition.
3. The flag field. This is one cell. A pointer to such a field is called a *flag field address* . For the meaning of the bits of the flag field see below.

4. The link field. This is one cell. A pointer to such a field is called a *link field address* . It contains the dictionary entry address of the last word that was defined in the same *word list* before this one.
5. The name field. This is one cell. This contains a pointer to a string. A pointer to such a field is called a *name field address* . The name itself is stored outside of the dictionary header in a regular string, i.e. a one cell count followed by as many characters, then padding for alignment. Unfortunately, *name token* is used in other Forth's to indicate a base to find other fields, what we call a *dictionary entry address*

This came about because the name is lowest in memory. In this Forth the code field address and the dictionary address happens to be the same. This has a small advantage in *next* , it needs no offset.

6. The source field. This is one cell. This can be used to hold a reference to the source, a block number or a pointer to a string. For kernel words it stays at zero.
7. Past the header . This is actually not a field, but the free roaming dictionary. However, most of the time the part of the dictionary space owned by a dictionary entry starts here. A pointer to such a field is called a *past header address* address . Mostly a *data field address* contains a pointer to just this address.

The entries are not only in alphabetic order, they are in order of essentiality. They are accessed by >CFA >DFA >FFA >LFA >NFA >SFA . (CREATE) takes care to generate the dictionary entry data structure; it is called by all defining words.

Note that *data field* has a specific meaning in the ISO standard. It is accessed through >BODY from the *execution token* while a data field address is accessed through >DFA from the *dictionary entry address* . It is in fact one cell behind where the *data field address* pointer points to. Furthermore only particular words have data fields, those defined by CREATE .

The flag bits used in the kernel are:

- The INVISIBLE bit = 1 when *smudge* d; this will prevent a match by (FIND) .
- The IMMEDIATE bit = 1 for IMMEDIATE definitions; it is called the *immediate bit* .
- The DUMMY bit = 1 for a dictionary header contained in the data of a namespace; this indicates that it should not be executed.
- The DENOTATION bit = 1 for a prefix word. This means that it is a short word used as a prefix that can parse all *denotation* 's (numbers) that start with that prefix, e.g. 7 or & . Usually it is a one character word, but not necessarily. All built-in prefix words are part of the minimum search order and are one character.

After the last letter of a name follow zero bytes up till the next cell boundary. The *code field* of all *colon definition* 's contains a pointer to the same code, the *inner interpreter* , called 'DOCOL'. For all words defined via 'CREATE ... DOES>' the code field contains the same code, 'DODOES'. On the other hand all *code definitions* (those written in assembler code) have different code fields.

At the *data field address* we find a pointer to an area with a length and content that depends on the type of the word.

- For a code word, it contains the same pointer as in the code field.
- For a word defined by CONSTANT , VARIABLE , USER , or DATA it has a width of one cell, and contains data. For VARIABLE it is a pointer to a cell, for DATA it is a pointer to a memory area of varying length.
- For all *colon definition* 's the data field address contains a pointer to an area of varying length. It contains the compiled high level code, a sequence of *dea* 's.
- For a word defined via 'CREATE ... DOES>' the first cell of this area contains a pointer to the *high level* code defined by DOES> and the remainder is data. A pointer to the data is passed to this DOES> code.

The wordset 'DICTIONARY' contains words for turning a *dictionary entry address* into any of these fields. They customarily start with >.

In summary, a dictionary falls apart into

1. Headers, with their fields.
2. Names, pointed to by some *name field address* .
3. Data, pointed to by some *data field address* . This includes high level code, that is merely data fed into the high level interpreter.
4. Code, pointed to by some *code field address* . This is directly executable machine code.

4.8.2 Details of memory layout

The disc buffers are mainly needed for source code that is fetched from disk where it resides in a file.

The disc buffer area is at the upper bound of RAM memory, So it ends at EM .

It is comprised of an integral number of buffers, each B/BUF bytes plus two cells. B/BUF is the number of bytes read from the disc in one go, originally thought of as one sector. In ciforth's B/BUF is always the size of one screen according to ISO : 1024 bytes. The constant _FIRST has the value of the address of the start of the first buffer. _LIMIT has the value of the first address beyond the top buffer. The distance between _FIRST and _LIMIT is a multiple of B/BUF bytes plus two cells.

For this ciforth the number of disk buffers is configured at 16 . The minimum possible is approximately 8 because nesting and locking requires that much blocks available at the same time.

The user area is configured to contain 0x40 cells, MAX-USER

contains the size of the area that is in use, in bytes. User variables can be added by the word USER , but you have to keep track yourself which offset in the user area can be used. Updating MAX-USER is recommended. The user area is just under the disc buffers. So it ends at _FIRST .

The console input buffer and the return stack share an area configured at a size of 0x100000 bytes. The lower half is intended for the console input buffer, and the higher part is used for the return stack, growing down from the end. The initial stack pointer is in variable R0 . The return stack grows downward from the user area toward the terminal buffer.

The computation stack grows downward from the terminal buffer toward the dictionary which grows upward. The initial stack pointer is in variable S0 .

During a cold start, the user variables are initialised from the bootup parameters to contain the addresses of the above memory assignments.

They can be changed. See Section 8.12.1 [+ORIGIN], page 75, for the bootup area. But take care. You probably need to study the source for how and when they take effect.

In multi-tasking a separate user area is allocated for each task, as well as a separate return stack area and a separate data stack area. A task that asks for input, also needs an extra console input buffer. A task is set up by allocating another area for all four. For task switching, it suffices to switch both stack pointers and the pointer to the user area.

4.8.3 Terminal I/O and vectoring.

It is useful to be able to change the behaviour of I/O words such that they put their output to a different channel. For instance they must output to the printer instead of to the console. In general this is called *vectoring* . Remember that in normal Forth system, all printing of numbers is to the terminal, not to a file or even a buffer. (On a linux system something like it can be accomplished by the redirection facilities available.) _HOSTED_MSDOS_((On a MSDOS system the need for this should be low, because of the redirection facilities available. However they are buggy.))

For this reason character output **CR** , **EMIT** and **TYPE** all go through a common word that can be changed. For **lina64** it is **TYPE** . Because this is defined in high level code it can temporarily be replaced by other code. This *revectoring* is possible for all high level words in **ciforth**, such that we need no special measures to make *vectoring* possible. As an example we replace **TYPE** by **MYTYPE** .

```
‘ ‘ MYTYPE >DFA @ ‘ TYPE >DFA ! ’
```

And back to default:

```
‘ ‘ TYPE >PHA ‘ TYPE >DFA ! ’
```

Be careful not to define **MYTYPE** in terms of **TYPE** , as a recursive tangle will result. This method works in all versions of **ciforth** and is called *revectoring* .

A similar technique is not so useful on the input side, because keys entered during **ACCEPT** are subject to correction until **<RET>** has been pressed. On **lina64** **ACCEPT** is left to the operating system, such that inputting to **lina64** has the same look and feel as other input. Text can be pasted in with the mouse, etc. Consequently **RUBOUT** is not used. This is a limitation but input direction supplied by the operating system goes a long way to alleviate this.

4.9 Libraries and options

In **ciforth** there is no notion of object (i.e. compiled) libraries, only of source libraries. A *Forth library* is a block file adorned with one convention. This is that the words defined in a screen are mentioned on the first line of that screen, the *index line* . This is of course quite established as a habit. The word **WANTED** takes a string and loads the first screen where that name occurs in the index line. For convenience also **WANT** is there that looks ahead in the input stream. These words are not in the kernel but are present in screen 1, that corresponds to the ‘-a’ option.

Screen 0 and screen 1 to 31 are reserved for options, some of which are available to be filled in by the user.

When a **Forth** is started up with a first parameter that is a one-letter option, the corresponding screen is to be executed. So ‘-a’ or ‘-A’ is equivalent to ‘1 LOAD’ and ‘-z’ or ‘-Z’ is equivalent to ‘26 LOAD’. In fact all options are mapped onto screen 0..31 by a bitwise and.

4.9.1 Options

ciforth is a primitive system, and can interpret just one option on the command line. If the first argument is not starting with - **ciforth** returns with error code 3. However the option ‘-1’ can bootstrap it into more sophisticated behaviour.

The following options can be passed to **lina64** on the command line:

- ‘-a’

Make sure **WANTED** is available. This is a copy of the ‘-w’ command because it is easier to remember ‘1 LOAD’ if the screen must be loaded manually. In addition the signon message is suppressed.

- ‘-c name’

Compile the file **name** to an executable binary. If **name** ends in ‘.frt’ it is omitted to arrive at the name of the binary, otherwise the binary is called **a.out**. Upon invocation of the binary the word defined latest is executed, then **Forth** goes **BYE** . **name** is a regular source file, not a block file. In addition **WANT** and **ARG[]** are made available.

- ‘-d name’ Include **name** with **[DEFINED]** available. This file can be made to load onto other **Forths** without modifications.

- ‘-e’

Load the elective screen, screen 5. This contains *preferences* , the tools you want to have available running an interactive **Forth**. The default library file contains system wide default

preferences. See the ‘-l’ option if the default preferences don’t suite you. In an elective screen you just put commands to load or execute at startup of an interactive session, such as ‘fortune -f /usr/lib/forthcookies" SYSTEM ’ or ‘WANT EDIT ’

- ‘-f forthcode’

Execute the ‘forthcode’ in the order present. Beware of the special characters in the shell. Also the shell will collapse multiple spaces into one.

- ‘-g number name’

Expand the system by ‘number’ Megabytes, then save it under the name ‘name’. ‘number’ may be negative, and in that case the system is made smaller.

- ‘-h’

Print overview of options.

- ‘-i binpath libpath [shellpath]’

Install the forth in ‘binpath’ and the library in ‘libpath’. If the ‘shellpath’ parameter is specified, it will be installed as the command interpreter used for SYSTEM. All of them must be full path names, not just directories. The ciforth that is running is copied to binpath, and the block file is copied to libpath.

For system wide installation on a modern large system the following is recommended:

```
su
./lina -g 60 lina+
./lina+ -i /usr/bin/lina /usr/lib/forth.lab
chmod 755 /usr/bin/lina
chmod 644 /usr/lib/forth.lab
```

For a smallish system you may expand by 0 Mbyte ‘-g 0’. If the system has no swap space, and less than 8 Mbyte of memory, use ‘-g -3’, diminish from 4 to 1 Mbyte. Expanding to the full size of the available RAM does no harm, as Linux overcommits memory.

- ‘--help’ ‘--version’ ‘--’ ‘-m’

The first option letter is trimmed to 5 bits, and excess characters are ignored. Thus all options that start with - are mapped onto m. The result is the combination of -h and -v, so both help and version information is printed. This conforms to the FSF-conventions.

- ‘-l name [more]’

Use a library ‘name’. Restart Forth with as a block file name and as options the remainder of the line shifted, such that ‘-l name’ disappears and the next option becomes the first. A file specified via ‘-l’ is opened for reading and writing. Options are again handled as described in the beginning of this section. In this way options may be added or reconfigured for personal use.

Note that the default file is opened for reading only.

- ‘-p’

Reserved option, not implemented.

Be pedantic about ISO. Redefine some words to follow the standard as closely as possible.

- ‘-q’

Be quiet, don’t give a startup message.

- ‘-s script’

Load the file script, but ignore its first line. This is intended to be used for Linux scripts, i.e. a piece of code to be interpreted rather than compiled. The first line is probably ‘#!lina -s’ or some such as ‘#!lina -l /usr/lib/forth/cgi/forth.lab -s’. In a script WANT and

`ARG[]` are available and you can use standard in and standard out. This follows the Unix conventions for script files. If you set the execute bit the file becomes a command and accepts arguments.

- ‘-t sourcefile’

Try to load the file `script` automatically, by possibly unsafe means. Report facilities that were required. This is a first step in a porting activity. Redefinition messages are issued on the error channel that can be redirected to `/dev/nul` leaving the report.

- ‘-v’

Print version and copy right information.

- ‘-w’

Make sure `WANTED` is available.

- ‘-?’

Give help, made to act the same as ‘-h’. The trimming makes that this is mapped to screen 31.

The remaining screens are available for options to be added at a later time, or for user defined options in a private library.

4.9.2 Private libraries

Working with source in files is quite comfortable using the default block library, especially if sufficient tools have been added to it. In principle all ISO words should be made available via `WANTED`.

In order to customize the forth library, you have to make a copy of the default `/usr/lib/ciforth/forth.lab` to your home directory, preferably to a lib subdirectory. Then you can start up using a ‘-l’ option. You can also use the ‘-i’ option to make a customized `lina64` in your project directory. See Chapter 4 [Manual], page 7, Subsection Configuring.

Most shells allow you to redefine commands, such as e.g. in bash:

```
alias lina='lina -l $HOME/lib/forth.lab'
```

Note that the ‘-l’ option hides itself, such that such an alias can be used completely identical to the original with respect to all options, including ‘-l’. Analysing arguments passed to `lina64` in your programs can remain the same.

4.9.3 Stand alone programs.

A stand alone program is made relying on the word `SAVE-SYSTEM`. A stand alone program may be an enhanced version of ciforth or a program with a special purpose, what in other languages is normally called a compiled program. In Forth parlance this is called a *turnkey application*, because mostly the program has special requirements from the environment. They are made using the word `TURNKEY`. They take a word, that is to be done, and a string with the file name. Unlike other Forths, the resulting program is a regular executable, that can be run on other computers with the same operating system. Generally an application ignores the absence of a library file. It must make sure to `CATCH` any possible errors and report them in terms of the situation the user is in. Otherwise the user will be confronted with raw Forth error numbers without even the one line description.

Mostly it is much easier to just use the ‘-c’ option. For a simple example See Chapter 4 [Manual], page 7, Getting Started Subsection Hello World!

5 Assembler

The assembler is described in this manual, because it is not feasible to use it from the description in the source. The assembler is a general framework, with plugins for different CPU's. It is a separate project called ciasdis. The i86 lina contains in its library an assembler that can assemble source code that has been debugged using ciasdis. Such a facility is not yet present for the ARM CPU. The information in this chapter is relevant because all assembler plugins just work on the ARM lina. The 8080 is a nice example because it is small, but the details about the Pentium plug in are only present in the i86 lina manual. This chapter is about the assembler itself, not about how it is used in relation with ciforth.

5.1 Introduction

Via '<http://home.hccnet.nl/a.w.m.van.der.horst/forthassembler.html>' you can find a couple of assemblers, to complement the generic ciforth system. The assemblers are not part of the lina64 package, and must be fetched separately.

They are based on the postit/fixup principle, an original and novel design to accommodate reverse engineering. The assembler that is present in the blocks, is code compatible, but is less sophisticated, especially regards error detection. This assembler is automatically loaded in its 16 or a 32 bit form, such that it is appropriate for adding small code definitions to the system at hand. The background information given here applies equally to that assembler.

A useful technique is to develop code using the full assembler. Then with code that at least contains valid instruction enter the debugging phase with the assembler from the library.

There is no assembler yet for 64 bit lina

ass.frt : the 80-line 8086 assembler (no error detection), a prototype.

as6809s.frt : a small 6809 assembler (no error detection).

asgen.frt : generic part of postit/fixup assembler

as80.frt : 8080 assembler, requires **asgen.frt**

asi86.frt : 8086 assembler, requires **asgen.frt**

asi386.frt : 80386 assembler, requires **asgen.frt**

aspentium.frt : general Pentium non-386 instructions, requires **asgen.frt**

asalpha.frt : ADDI , , -1 Alpha assembler, requires **asgen.frt**

asi6809.frt : 6809 assembler, requires **asgen.frt**

ps.frt : generate opcode sheets

p0.asi386.ps : first byte opcode for asi386 assembler

p0F.asi386.ps : two byte opcode for same that start with 0F.

test.mak : makefile, i.e. with targets for opcode sheets.

De **asi386.frt** (containing the full 80386 instruction set) is in many respects non-compliant to Intel syntax. The instruction mnemonics are redesigned in behalf of reverse engineering. There is a one to one correspondence between mnemonics and machine instructions. In principle this would require a monumental amount of documentation, comparable to parts of Intel's architecture manuals. Not to mention the amount of work to check this. I circumvent this. Opcode sheets for this assembler are generated by tools automatically, and you can ask interactively how a particular instructions can be completed. This is a viable alternative to using manuals, if not more practical. (Of course someone has to write up the descriptions, I am happy Intel has done that.).

So look at my opcode sheets. If you think an instruction would be what you want, use **SHOW**: to find out how it is to be completed. If you are at all a bit familiar, most of the time you can understand what your options are. If not compare with an Intel opcode sheet, and look up the

instruction that sits on the same place. If you don't understand them, you can still experiment in a Forth to find out.

The assembler in the Library Addressable by Blocks (block file) hasn't the advanced features of disassembly, completion and error detection. It is intended for incidental use, to speed up a crucial word. But the code is fully compatible, so you can develop using the full assembler.

5.2 Reliability

I skimmed on write up. I didn't skimp on testing. All full assemblers, like `asi386.frt` and `asptium.frt`, are tested in this way:

1. All instructions are generated. (Because this uses the same mechanism as checking during entry, it is most unlikely that you will get an instruction assembled that is not in this set.)
2. They are assembled.
3. They are disassembled again and compared with the original code, which must be the same.
4. They are disassembled by a different tool (GNU's `objdump`), and the output is compared with 3. This has been done manually, just once.

This leaves room for a defect of the following type: A valid instruction is rejected or has been totally overlooked.

But opcode maps reveal their Terra Incognita relentlessly. So I am quite confident to promise a bottle of good Irish whiskey to the first one to come up with a defect in this assembler.

The full set of instructions, with all operand combinations sit in a file for reference. This is all barring the 256-way 'SIB' construction and prefixes, or combinations thereof. This would explode this approach to beyond the practical. Straightforward generation of all instructions is also not practical for the Alpha with 32K register combinations per instruction. This is solved by defining "interesting" registers that are used as examples and leaving out opcode-operand combinations with uninteresting registers.

5.3 Principle of operation

In making an assembler for the Pentium it turns out that the in-between-step of creation defining words for each type of assembly gets in the way. There are just too many of them.

MASM heavily overloads the instruction, in particular 'MOV'. Once I used to criticise Intel because they had an unpleasant to use instruction set with 'MOV' 'MVR' and 'MVI' for move instructions. In hindsight I find the use of different opcodes correct. (I mean they are really different instructions, it might have been better if they weren't. But an assembler must live up to the truth.) Where the Intel folks really go overboard is with the disambiguation of essentially ambiguous constructs, by things as 'OFFSET' 'BYTE POINTER' 'ASSUME'. You can no longer find out what the instruction means by itself.

A simple example to illustrate this problem is

```
INC [BX]
```

Are we to increment the byte or the word at BX? Intel's solution is

```
INC BYTE POINTER BX
```

Contrarily here we adapt the rule: if an instruction doesn't determine the operand size (some do, like `LEA`,), then a size fixup is needed ('X|' or 'B|').

In this assembler this looks like

```
INC, B| Z0| [BX]
```

This is completely unambiguous.

These are the phases in which this assembler handles an instruction:

- POSTIT phase: MOV, assembles a two byte instruction with holes.
- FIXUP phase: X| or B| fits in one of the holes left. Other fixups determine registers and addressing mode.
- COMMA phase: First check whether the fixups have filled up all holes. Then add addresses (or offsets) and/or immediate data, using e.g. IL, or L,
- Check whether all commaers, requested either by postit's or fixup's are present. This check is actually executed by the next postit prior to assembling, or by END-CODE .

Doesn't this system lay a burden on the programmer? Yes. He has to know exactly what he is doing. But assembly programming is dancing on a rope. The Intel syntax tries to hide from you where the rope is. A bad idea. There is no such thing as assembly programming for dummies.

An advantage is that you are more aware of what instructions are there. Because you see the duplicates.

Now if you are serious, you have to study the `asgen.frt` and `as80.frt` sources. You better get your feet wet with `as80.frt` before you attack the Pentium. The way 'SIB' is handled is so clever, that sometimes I don't understand it myself. It deviates somewhat from the phases explained here.

Another invention in this assembler is the *family of instructions* . Assembler instructions are grouped into families with identical fixups, and a increment for the opcodes. These are defined as a group by a single execution of a defining word. For each group there is one opportunity to get the opcode wrong; formerly that was for each opcode.

5.4 The 8080 assembler

The 8080 assembler doesn't take less place than Cassady's . (In the end the postit-fixup makes the Pentium assembler more compact, but not the 8080.) But... The regularities are much more apparent. It is much more difficult to make a mistake with the code for the 'ADD' and 'ADI' instructions. And there is information there to the point that it allows to make a disassembler that is independent of the instruction information, one that will work for the 8086, look at the pop family. First I had

```
38 C1 02 4 1FAMILY, POP-- PUSH RST      ( B'|)
```

(cause I started from an existing assembler.) But of course RST (the restart instruction) has nothing to do with registers, so it gets separated out. Then the exception, represented by the hole '--' disappears. The bottom line is : the assembler proper now takes 22 lines of code. Furthermore the "call conditional" and "return conditional" instructions were missing. This became apparent as soon as I printed the opcode sheets. For me this means turning "jump conditional" into a family.

5.5 Opcode sheets

Using `test.mak` (on a linux computer in lina) you can generate opcode sheets by "`make asi386.ps`". For the opcode sheets featuring a n-byte prefix you must pass the 'PREFIX' to make and a 'MASK' that covers the prefix and the byte opcode, e.g. '`make asi386.ps MASK=FFFF PREFIX=0F`'. The opcode sheets `p0.asi386.ps` and `p0F.asi386.ps` are already part of the distribution and can be printed on a PostScript printer or viewed with e.g. 'gv'.

Compare the opcode sheets with Intel's to get an overview of what I have done to the instruction set. In essence I have re-engineered it to make it reverse assemblable, i.e. from a

disassembly you can regenerate the machine code. This is **not** true for Intel's instruction set, e.g. Intel has the same opcode for 'MOV, X| T| AX'| R| BX| ' and 'MOV, X| F| BX'| R| AX| '.

To get a reminder of what instructions there are type `SHOW-OPCODES` . If you are a bit familiar with the opcodes you are almost there. For if you want to know what the precise instruction format of e.g. `IMUL|AD`, just type '`SHOW: IMUL|AD`,' You can also type `SHOW-ALL`, but that takes a lot of time and is more intended for test purposes. The most useful of them all is ??

that for a partially completed instruction shows all possible completions.

5.6 Assembler Errors

Errors are identified by a number. They are globally unique, so assembler error numbers do not overlap with other ciforth error numbers, or errors returned from operating system calls. Of course the error numbers are given in decimal, always.

The errors whose message starts with 'AS:' are used by the PostIt FixUp assembler in the file `asgen.frt`. See Chapter 6 [Errors], page 29, for other errors.

- 'ciforth ERROR # 26 : AS: PREVIOUS INSTRUCTION INCOMPLETE'

You left holes in the instruction before the current one, i.e. one or more fixups like `X|` are missing. Or you forget to supply data required by the opcode like `OW`, . With `SHOW:` you can see what completions of your opcode are legal.

- 'ciforth ERROR # 27 : AS: INSTRUCTION PROHIBITED IRREGULARLY'

The instruction you try to assemble would have been legal, if Intel had not made an exception just for this combination. This situation is handled by special code, to issue just this error.

- 'ciforth ERROR # 28 : AS: UNEXPECTED FIXUP/COMMAER'

You try to complete an opcode by fixup's (like `X|`) or comma-ers (like `OW`,) in a way that conflicts with what you specified earlier. So the fixup/comma-er word at which this error is detected conflicts with either the opcode, or one of the other fixups/comma-ers. For example `B|` (byte size) with a `LEA`, opcode or with a `DI|` operand.

- 'ciforth ERROR # 29 : AS: DUPLICATE FIXUP/UNEXPECTED COMMAER'

You try to complete an opcode by fixup's (like `X|`) or comma-ers (like `OW`,) in a way that conflicts with what you specified earlier. So the fixup/comma-er word at which this error is detected conflicts with either the opcode, or one of other fixups/comma-ers. For example `B|` (byte size) with a `LEA`, opcode or with a `DI|` operand.

- 'ciforth ERROR # 30 : AS: COMMAERS IN WRONG ORDER'

The opcode requires more than one data item to be comma-ed in, such as immediate data and an address. However you put them in the wrong order. Use `SHOW:` .

- 'ciforth ERROR # 31 : AS: DESIGN ERROR, INCOMPATIBLE MASK'

This signals an internal inconsistency in the assembler itself. If you are using an assembler supplied with ciforth, you can report this as a defect ("bug"). The remainder of this explanation is intended for the writers of assemblers. The bits that are filled in by an assembler word are outside of the area were it is supposed to fill bits in. The latter are specified separately by a mask.

- 'ciforth ERROR # 32 : AS: PREVIOUS OPCODE PLUS FIXUPS INCONSISTENT'

The total instruction with opcode, fixups and data is "bad". Somewhere there are parts that are conflicting. This may be another one of the irregularities of the Intel instruction set. Or the `BAD` data was preset with bits to indicate that you want to prohibit this instruction on this processor, because it is not implemented. Investigate `BAD` for two consecutive bits that are up, and inspect the meaning of each of the two bits.

6 Errors

Errors are uniquely identified by a number. The error code is the same as the **THROW** code. In other words the Forth exception system is used for errors. A ciforth error always displays the text “ciforth ERROR #” plus the error number, immediately and directly. Of course the error numbers are given in decimal, irrespective of **BASE** . This allows you to look the error up in the section “Error explanations”. More specific problems are addressed in the section “Common Problems”.

6.1 Error philosophy

If you know the error number issued by ciforth, the situation you are in is identified, and you can read an explanation in the next section. Preferably in addition to the number a *mnemonic message* is displayed. It is fetched from the *library file* . But this is not always possible, such is the nature of error situations. A mnemonic message has a size limited to 63 characters and is therefore seldomly a sufficient explanation.

A good error system gives additional specific information about the error. In a plain ciforth this is limited to the input line that generated the error. Via the library file you may install a more sophisticated error reporting, if available.

Within ciforth itself all error situation have their unique identification. You may issue errors yourself at your discretion using **THROW** or, preferably, **?ERROR** and use an error number with an applicable message. However, unless yours is a quick and dirty program, you are encouraged to use some other unique error number.

6.2 Common problems

6.2.1 Error 11 or 12 caused by lower case.

If you type a standard word like **words** in lower case, it will not be recognised, resulting in error 11. Similarly **' words** results in error 12. This is because the names as defined in the standard are in upper case and **lina64** is *case sensitive* , i.e. the difference between lower and upper case is significant and only words that match in this respect too are found in the dictionary.

After **'1 LOAD** or if started up using **'lina -a** or **'lina -r** you have **WANTED** and **WANT** available. You may now issue **' WANT CASE-INSENSITIVE** and switch the system into case-insensitivity and back by issuing the words **CASE-INSENSITIVE** and **CASE-SENSITIVE** .

Case insensitivity applies to the words looked up in the dictionary, not to hex digits.

6.2.2 Error 8 or only error numbers

If you get an error 8 as soon as you try to **LOAD** or **LIST** a screen or use an option, or if errors show up only as numbers without the mnemonic message, this is because you cannot access the library file. It may not be there, or it may not be at the expected place. ciforth contains a string **BLOCK-FILE** , that contains the name of the library file interpreter, with as a default **forth.lab**. If this is not correct you may change it as appropriate by e.g.

"/usr/lib/ciforth/forth.lab" BLOCK-FILE \$! ' The library is accessible for read and write access and mnemonic message will be fetched from it, after you install it with **'2 BLOCK-INIT 1 WARNING !'**.

6.2.3 Error 8 while editing a screen

If after editing a screen, you get error 8, the screen has not been written to disk, because you have no write access for the library file. You must issue `DEVELOP` which reopens the library file in `READ_WRITE` mode. Normally this should be part of loading the `EDITOR`. It may be of course that you don't have privilege to write to the file. As non-privileged user you cannot edit the system-wide library file.

You may always edit and use a private copy of the library file, by the `'-1'` option. See Chapter 4 [Manual], page 7, for how options work. The `'-1'` option itself works only if at least the official library file has been correctly installed.

6.2.4 Error -13 while trying I/O

If you get an error -13 this means you have insufficient privilege for an operation. An unexpected situation that provokes this error may be any access to io ports like general io *gpio*

or reading the clock. For those accesses one has to be root.

6.3 Error explanations

This section shows the explanation of the errors in ascending order. In actual situations sometimes you may not see the part after the semi colon. If in this section an explanation is missing, this means that the error is given for reference only; the error cannot be generated by your *lina64*, but maybe by other version of *ciforth* or even a differently configured *lina64*. For example for a version without security you will never see error 1. If it says "not used", this means it is not used by any *ciforth*.

The errors whose message starts with `'AS:'` are used by the PostIt FixUp assembler in the file `asgen.frt`, (see Chapter 5 [Assembler], page 25).

Negative error numbers are those reported by Linux. If possible, mnemonic error messages are shown. An explanation of the error is available in the manuals only.

`'ciforth ERROR # -2 : No such file '`

is an example of a Linux message. .

Here are the error explanations.

- `'ciforth ERROR # XXX : (NO TEXT MESSAGE AVAILABLE FOR THIS ERROR)'`

This is the only messages that is common to more errors, anything goes at the place of XXX. It means that information about this error is not in the library, but the error number remains to identify the error. The error number is probably used by user programs and hopefully documented there. So you can allocate error numbers not yet in use, and use them to identify your error situations. You can add messages to the library, but errors outside of the range `[-256 63]` need a re-assembly of the source, using adapted values of `M4_ERRORMIN` `M4_ERRORMAX`.

- `'ciforth ERROR # 1 : EMPTY STACK'`

The stack has underflowed. This is detected by `?STACK` at several places, in particular in `INTERPRET` after each word interpreted or compiled. There is ample slack, but malicious intent can crash the system before this is detected.

- `'ciforth ERROR # 2 : DICTIONARY FULL'`

Not used.

- `'ciforth ERROR # 3 : FIRST ARGUMENT MUST BE OPTION'`

If you pass arguments to *ciforth*, your first argument must be an option (such as `-a`), otherwise it doesn't know what to do with it.

- ‘ciforth ERROR # 4 : ISN'T UNIQUE’

Not being unique is not so much an error as a warning. The word printed is the latest defined. A word with the same name exists already in the current search order.

- ‘ciforth ERROR # 5 : EMPTY NAME FOR NEW DEFINITION’

An attempt is made to define a new word with an empty string for a name. This is detected by (CREATE) . All *defining word* can return this message. It is typically caused by using such a word at the end of a line.

- ‘ciforth ERROR # 6 : DISK RANGE ?’

Reading to the terminal input buffer failed. The message is probably inappropriate.

- ‘ciforth ERROR # 7 : FULL STACK’

The stack has run into the dictionary. This can be caused by pushing too many items, but usually it must be interpreted as dictionary full. If you have enough room, you have passed a wrong value to ALLOT . This is detected at several places, in particular in INTERPRET after each word interpreted.

- ‘ciforth ERROR # 8 : ERROR ACCESSING BLOCKS FROM MASS STORAGE’

An access to the Library Accessible by Block (screen aka block file) has failed. Or if you are an advanced user, and used the block system at your own discretion, it simply means that access to the blocks has failed.

This is detected by ?DISK-ERROR called from places where a disk access has occurred. It may be that the library file has not been properly installed. Check the content of BLOCK-FILE . You may not have the right to access it. Try to view the file. Normally the library file is opened read-only. If you want to edit it make sure to do DEVELOP in order to reopen it in read/write mode. If you forget, you get this message too.

- ‘ciforth ERROR # 9 : UNRESOLVED FORWARD REFERENCE’

A word can be compiled before it is fully defined, with a standard idiom like DEFER or ciforth idiom :F . If it is still not fully defined when it is used, this error is issued.

- ‘ciforth ERROR # 10 : NOT A WORD, NOR A NUMBER OR OTHER DENOTATION’

The string printed was not found in the dictionary as such, but its first part matches a *denotation* . The denotation word however rejected it as not properly formed. An example of this is a number containing some non-digit character, or the character denotation & followed by more than one character. It may also be a miss-spelled word that looks like a number, e.g. ‘25WAP’ . Be aware that denotations may mask regular words. This will only happen with user-defined denotations. Built-in denotations are in the ONLY namespace, that can only be accessed last, because it ends the search order. Note that hex digits must be typed in uppercase, even if "CASE-SENSITIVE" is in effect. Error 10 may be caused by using lower case where upper case is expected, such as for ISO standard words. See the section "Common problems" in this chapter if you want to make ciforth case insensitive.

- ‘ciforth ERROR # 11 : WORD IS NOT FOUND’

The string printed was not found in the dictionary. This error is detected by ’ (tick). This may be caused by using lower case where upper case is required for ISO standard words. See the section "Common problems" in this chapter if you want to make ciforth case insensitive.

- ‘ciforth ERROR # 12 : NOT RECOGNIZED’

The string printed was not found in the dictionary, nor does it match a number, or some other denotation. This may be caused by using lower case where upper case is required for ISO standard words or for hex digits. See the section "Common problems" in this chapter if you want to make ciforth case insensitive.

- ‘ciforth ERROR # 13 : ERROR, NO FURTHER INFORMATION’
This error is used temporarily, whenever there is need for an error message but there is not yet one assigned.
- ‘ciforth ERROR # 14 : SAVE/RESTORE MUST RUN FROM FLOPPY’
- ‘ciforth ERROR # 15 : CANNOT FIND WORD TO BE POSTPONED’
The word following POSTPONE must be postponed, but it can’t be found in the search order.
- ‘ciforth ERROR # 16 : CANNOT FIND WORD TO BE COMPILED’
The word following [COMPILE] must be postponed, but it can’t be found in the search order.
- ‘ciforth ERROR # 17 : COMPILATION ONLY, USE IN DEFINITION’
This error is reported by ?COMP . You try to use a word that doesn’t work properly in interpret mode. This mostly refers to control words like IF and DO . If you want control words to work in interpret mode, use WANT -scripting- .
- ‘ciforth ERROR # 18 : EXECUTION ONLY’
This error is reported by ?EXEC. . You try to use a word that doesn’t work properly in compile mode. You will not see this error, because all words in ciforth do.
- ‘ciforth ERROR # 19 : CONDITIONALS NOT PAIRED’
This error is reported by ?PAIRS . You try to improperly use control words that pair up (like IF and THEN , or DO and LOOP)
This detection mechanism makes it impossible to compile some constructions allowed by the ISO standard. You may disable this checking by NO-SECURITY and re-instate it by DO-SECURITY .
- ‘ciforth ERROR # 20 : STACK UNBALANCE, STRUCTURE UNFINISHED?’
This error is reported by ?CSP . It detects stack unbalance between : and ; , or wherever you choose to use the words !CSP and ?CSP . This means there is an error in the compiled code. This message is given also if during compilation you try to use data that is put on the stack before : . Instead of
‘<generatedata> : name LITERAL ;’
use
‘<generatedata> : name [_ SWAP] LITERAL ; DROP’
to keep the stack at the same depth.
- ‘ciforth ERROR # 21 : IN PROTECTED DICTIONARY’
The word you are trying to FORGET is below the FENCE , such that forgetting is not allowed.
- ‘ciforth ERROR # 22 : USE ONLY WHEN LOADING’
This error is reported by ?LOAD . You try to use a word that only works while loading from the BLOCK-FILE , in casu --> .
- ‘ciforth ERROR # 23 : OFF CURRENT EDITING SCREEN’
- ‘ciforth ERROR # 24 : (WARNING) NOT PRESENT, THOUGH WANTED’ This error is reported by WANTED . The word you required, has been looked up in the index lines. It was not found in the index lines, or it was a dummy item, that only marks the screen to be loaded, e.g. ‘-scripting-’. In the latter case it can be safely ignored. This **must** be a warning only, because compilation can still succeed if the word is supplied by other means, in particular conditional compilation.
- ‘ciforth ERROR # 25 : LIST EXPECTS DECIMAL’
This message is used by a redefined LIST , to prevent getting the wrong screen.

- ‘ciforth ERROR # 48 : NO BUFFER COULD BE FREED, ALL LOCKED’

While a block is in use by `THRU`, it is *locked*, which means that it must stay in memory. In addition blocks can be locked explicitly by `LOCK`. If a free block is needed, and there is no block that can be written back to the mass storage (disk or flash), you get this error.

- ‘ciforth ERROR # 49 : EXECUTION OF EXTERNAL PROGRAM FAILED’ The word `SYSTEM` detected an error while trying to execute an external program.
- ‘ciforth ERROR # 50 : NOT ENOUGH MEMORY FOR ALLOCATE’ The dynamic memory allocation could not allocate a buffer of the size wanted, because there is not enough consecutive memory available. Fragmentation can cause this to happen while there is more than that size available in total. This is detected by `ALLOCATE` or `RESIZE`.
- ‘ciforth ERROR # 51 : UNKNOWN FORMAT IDENTIFIER’ This error is detected by the `FORMAT` wordset. The word following `%` in a format string, is not known. This means that it is not present in the *namespace* `FORMAT-WID`.

See Section 8.29.2 [ASSEMBLER], page 114,, for errors generated by the assembler. In general these have numbers that are higher than the general errors.

7 Documentation summary

The most important Forth site is <http://www.forth.org> with links to all Forth chapters and commercial and free Forth implementation.

Like all modern languages the Forth ISO standard is available on the web <http://www.taygeta.com/forth/dpans.htm>

The official, printed manual by the American National Standards Institute commands a stiff price.

Starting Forth by Leo Brodie

A classic still worth reading, despite its age. You must adapt the examples in order to use it with an ISO Forth, A modernized version is available online at <http://www.forth.com/starting-forth/>

Going Forth by Leo Brodie

More timeless, maybe even more important, about the philosophy of Forth.

The German Fig Chapter has a publication: Vierte Dimension.

For historic interest the following is copied from the FIG documentation 1978.

Caltech FORTH Manual, an advanced manual with internal details of Forth. Has Some implementation peculiarities. The Caltech Book Store, Pasadena, CA.

Kitt Peak Forth Primer, edited by the Forth Interest Group, P. O. Box 1105, San Carlos, CA 94070.

microFORTH Primer, Forth, Inc. 815 Manhattan Ave. Manhattan Beach, CA 90266

Forth Dimensions, newsletter of the Forth Interest Group, \$5.00 for 6 issues including membership. F-I-G. P.O. Box 1105, San Carlos, CA. 94070

8 Glossary

Wherever it says single precision number or *cell* 64 bits is meant. Wherever it says *double* or “double precision number” a 128 bits number is meant.

The first line of each entry shows a symbolic description of the action of the procedure on the parameter stack. The symbols indicate the order in which input parameters have been placed on the stack. The dashes “—” indicate the execution point; any parameters left on the stack are listed. In this notation, the top of the stack is to the right. Any symbol may be followed by a number to indicate different data items passed to or from a Forth word.

The symbols include:

‘ addr ’	memory address
‘ b ’	8 bit byte (the remaining bits are zero)
‘ c ’	7 bit ascii character (the remaining bits are zero)
‘ d ’	128 bit signed double integer: most significant portion with sign on top of stack
‘ dea ’	A <i>dictionary entry address</i> , the basic address of a Forth word from which all its fields can be found.
‘ f ’	logical <i>flag</i> : zero is interpreted as false, non-zero as true
‘ faraddr ’	a <selector:address> pair
‘ ff ’	<i>Forth flag</i> , a well-formed logical flag, 0=false, -1=true.
‘ false ’	a false <i>Forth flag</i> : 0
‘ n ’	64 bit signed integer number; it is also used for a 64-bit entity where it is irrelevant what number it represents
‘ sc ’	a <i>string constant</i> , i.e. two cells, an address and a length; length characters are present, starting at the address (they must not be changed)
‘ true ’	a true <i>Forth flag</i> : -1.
‘ u ’	64-bit unsigned integer, also used whenever a cell is considered as a bitset.
‘ ud ’	128-bit unsigned double integer: most significant portion on top of stack

The capital letters on the right show definition characteristics:

‘ C ’	May only be used within a colon definition. A digit indicates number of memory addresses used, if other than one.
‘ E ’	Intended for execution only.
‘ FIG ’	Belongs to the FIG model
‘ I ’	Has immediate bit set. Will execute even when compiling.
‘ ISO ’	Belongs to ISO standard
‘ NFIG ’	Word belongs to FIG standard, but the implementation is not quite conforming.
‘ NISO ’	Word belongs to ISO standard, but the implementation is not quite conforming.
‘ WANT ’	Word is not in the kernel, use the WANT to load it from the library. These words are maintained and tested, will only be changed with notice and an upgrade pad will be supplied.
‘ U ’	A user variable.

Where there is mention of a standard or a model, it means that the word actually complies to the standard or the model, not that some word of that name is present. Words marked with ‘ISO,FIG’ will behave identically over all but the whole spectra of Forth’s.

Unless otherwise noted, all references to numbers are for 64-bit signed integers. For 128-bit signed numbers, the most significant part (with the sign) is on top.

All arithmetic is implicitly 64-bit signed integer math, with error and under-flow indication unspecified.

A *nil pointer* is an address containing zero. This indicates an invalid address.

The Forth words are divided into *wordsets*, that contain words that logically belong together. Each wordset has a separate section with a description. The following rules take precedence over any wordset a word may logically belong to.

- A defining word — one that adds to the dictionary — is present in the wordset ‘DEFINING’.
- A denotation word — one that has the prefix bit set — is present in the wordset ‘DENOTATIONS’.
- An environmental query word — one that is understood by ?ENVIRONMENT — is present in the wordset ‘ENVIRONMENTS’.

8.1 BLOCKS

The block mechanism connects to the Forth system a single background storage divided in numbered *blocks*. The wordset ‘BLOCKS’ contains words to input and output to this mass storage. In this ciforth blocks reside in a file, by default named `forth.lab`. Most blocks are used for the ‘SCREEN’ facility, where each block contains source code.

8.1.1 #BUFF

Name: #BUFF

Stackeffect: — n

Attributes:

Description: A constant that leaves the number of block buffers. Because a buffer that is being interpreted is locked in memory, this is also a limit to the nesting depth of blocks loading other blocks.

See also: ‘BLOCK’ ‘THRU’ ‘LOAD’ ‘LOCK’

8.1.2 -->

Name: -->

No stackeffect

Attributes: I,WANT

Description: Continue interpretation with the next disc screen. If the current input source is not from a block, a crash will ensue. If this new screen is left by throw of an exception, the screen may remain locked until a QUIT, or any uncaught exception.

See also: ‘LOCK’ ‘CATCH’ ‘LOAD’

8.1.3 ?DISK-ERROR

Name: ?DISK-ERROR

Stackeffect: n—

Attributes:

Description: Interpret ‘n’ as the status of a disk i/o call and *signal an error* if it contains an error condition. It is only used to signal errors related to accessing the BLOCK-FILE.

See also: ‘BLOCK-FILE’ ‘BLOCK-HANDLE’ ‘BLOCK-INIT’ ‘BLOCK-EXIT’

8.1.4 B/BUF

Name: B/BUF

Stackeffect: — n

Attributes:

Description: This constant leaves the number of bytes per disc buffer, the byte count read from disc by **BLOCK** . The ISO standard fixes this to 1024.

See also: ‘(BUFFER)’

8.1.5 BLOCK-EXIT

Name: BLOCK-EXIT

Stackeffect: —

Attributes:

Description: A block file must have been opened by **BLOCK-INIT** . All blocks are unlocked. Any changed blocks are written back to mass storage. Close the currently open block file **BLOCK-HANDLE** , i.e. the mass storage words no longer work, and will result in error messages. If error messages were fetched from disk, they no longer are.

See also: ‘BLOCK’ ‘LIST’ ‘LOAD’ ‘DISK-ERROR’ ‘WARNING’

8.1.6 BLOCK-FILE

Name: BLOCK-FILE

Stackeffect: —addr

Attributes:

Description: Leave the address ‘**addr**’ of a counted string, the name of a *library file*

in which *blocks* are (to be) allocated. The name may contain a path and be at most 252 characters long. The default name is **forth.lab** . This name may be changed and is used by the **BLOCK-INIT** command.

See also: ‘BLOCK-HANDLE’ ‘BLOCK-INIT’ ‘BLOCK-EXIT’ ‘\$@’

8.1.7 BLOCK-HANDLE

Name: BLOCK-HANDLE

Stackeffect: —n

Attributes:

Description: Leave a file handle in ‘**n**’ . If it is negative there is no block file open, otherwise the handle is used by the system to access blocks.

See also: ‘BLOCK-FILE’ ‘BLOCK-INIT’ ‘BLOCK-EXIT’

8.1.8 BLOCK-INIT

Name: BLOCK-INIT

Stackeffect: n —

Attributes:

Description: Map the blocks on the block file **BLOCK-FILE** , i.e. the mass storage words refer to the blocks in this file. The handle ‘**BLOCK-HANDLE**’ can be used to access it, with access code ‘**n**’ (2 for read and write). This command signals failure by a negative handle in **BLOCK-HANDLE** . You must activate mnemonic error messages explicitly by setting **WARNING** .

See also: ‘BLOCK’ ‘LIST’ ‘LOAD’ ‘BLOCK-EXIT’ ‘OPEN-FILE’

8.1.9 BLOCK-READ

Name: BLOCK-READ

Stackeffect: addr blk —

Attributes:

Description: The ciforth primitive for reading of blocks. ‘addr’ specifies the destination block buffer, ‘blk’ is the sequential number of the referenced physical block BLOCK-READ determines the location on mass storage, performs the read and throws an exception on errors.

See also: ‘BLOCK’ ‘DISK-ERROR’ ‘BLOCK-WRITE’

8.1.10 BLOCK-WRITE

Name: BLOCK-WRITE

Stackeffect: addr blk —

Attributes:

Description: The ciforth primitive for writing of blocks. ‘addr’ specifies the source or destination block buffer, ‘blk’ is the sequential number of the referenced physical block. BLOCK-WRITE determines the location on mass storage, performs the write and throws an exception on errors.

See also: ‘BLOCK’ ‘DISK-ERROR’ ‘BLOCK-READ’

8.1.11 BLOCK

Name: BLOCK

Stackeffect: n — addr

Attributes: ISO,FIG

Description: Leave ‘addr’, the disc buffer containing block ‘n’, which is the physical disk block ‘OFFSET+n’. The address left is the field within the buffer to be used for data storage. If the block is not already in memory, it is transferred from disc to a new buffer allocated by (BUFFER) . Blocks are generally used to contain source code to be interpreted by LOAD . They can be equally useful to contain other data, e.g. for implementing a database.

See also: ‘(BUFFER)’ ‘BLOCK-READ’ ‘BLOCK-WRITE’ ‘OFFSET’ ‘UPDATE’ ‘FLUSH’ ‘LOAD’

8.1.12 DISK-ERROR

Name: DISK-ERROR

Stackeffect: — addr

Attributes:

Description:

This variable is not used in ciriscv.lina64.html, errors are thrown..

See also: ‘BLOCK’

8.1.13 EMPTY-BUFFERS

Name: EMPTY-BUFFERS

No stackeffect

Attributes: ISO,FIG

Description: Mark all block-buffers as empty. Updated blocks are not written to the disc. This is an initialization procedure before first use of the disc. The usage as an “undo” is infeasible in ciforth.

See also: ‘FLUSH’ ‘BLOCK’ ‘SCREEN’ ‘UPDATE’

8.1.14 UPDATE

Name: UPDATE

No stackeffect

Attributes: ISO,FIG

Description: Marks the most recently referenced block (pointed to by `_PREV`) as altered. The block will subsequently be transferred automatically to disc should its buffer be required for storage of a different block. In fact the block is transferred to disk immediately.

See also: 'BLOCK' 'EMPTY-BUFFERS'

8.1.15 (BUFFER)

Name: (BUFFER)

Stackeffect: n — addr

Attributes:

Description: Return the address 'addr' of a buffer assigned to block 'n'. The buffer layout is as follows: a cell with the block number, a cell with the status, and the content. The status is negative for locked, zero for free and one for present and unlocked. The block is not read from the disc. The buffer is either one that was already assigned, or else a free buffer. If there is none free, some non-locked buffer is freed. The contents of that buffer is written to the disc, if it was marked as updated. In ciforth this is never needed, because updated blocks are written immediately. In ciforth blocks can be locked, and locked buffers are never freed by (BUFFER). An update flag would somehow be multiplexed with the lock count, but it is not needed in this ciforth. If all buffers were locked, (BUFFER) throws exception 48.

See also: 'BLOCK' '_PREV' '#BUFF' 'LOCK' 'UNLOCK'

8.1.16 +BUF

Name: +BUF

Stackeffect: addr1 — addr2 ff

Attributes: FIG

Description: Advance the disc buffer address 'addr1' to the address of the next buffer 'addr2'. Boolean 'ff' is false when 'addr2' is the buffer presently pointed to by variable `_PREV`.

See also: 'BLOCK'

8.1.17 BLOCK-SEEK

Name: BLOCK-SEEK

Stackeffect: n—

Attributes:

Description: A block file must have been opened by BLOCK-INIT. Position the file pointer at block 'n' in behalf of subsequent reads and writes.

See also: 'BLOCK' 'LIST' 'LOAD'

8.1.18 FLUSH

Name: FLUSH

No stackeffect

Attributes: ISO,FIG

Description: Make sure that the content of all UPDATE d block buffers has been transferred to disk. The buffers are no longer associated with a block and their content is no longer available. In ciforth no transfer takes place, because mass storage is updated automatically in the background.

See also: 'EMPTY-BUFFERS' 'BLOCK' 'SCREEN'

8.1.19 OFFSET

Name: **OFFSET**

Stackeffect: — addr

Attributes: U

Description: A user variable which contains a block offset to disc drives; in this way a part of it is available for boot-code.

As blocks are allocated in a file on the host operating system it is 0. The contents of **OFFSET** is added to the stack number by **BLOCK** before read or writing blocks.

See also: ‘**BLOCK**’ ‘**MESSAGE**’ ‘**BLOCK-READ**’ ‘**BLOCK-WRITE**’

8.1.20 _FIRST

Name: **_FIRST**

Stackeffect: — addr1

Attributes:

Description: A constant that leaves the address of the first (lowest) block buffer.

See also: ‘**BLOCK**’ ‘**_LIMIT**’

8.1.21 _LIMIT

Name: **_LIMIT**

Stackeffect: — addr1

Attributes:

Description: A constant leaving the address just above the highest memory available for a disc buffer. Actually this is the highest system memory.

See also: ‘**BLOCK**’ ‘**_FIRST**’

8.1.22 _PREV

Name: **_PREV**

Stackeffect: — addr

Attributes:

Description: A variable containing the address of the disc buffer (not its content field!) most recently referenced. The **UPDATE** command marks this buffer to be written to disc.

See also: ‘**(BUFFER)**’

8.2 COMPILING

The wordset ‘**COMPILING**’ contains words that compile See Section 8.6.14 [IMMEDIATE], page 60, words and numbers. You need special precautions because these words would execute during compilation. Numbers are compiled *in line*, behind a word that fetches them.

8.2.1 DLITERAL

Name: **DLITERAL**

Stackeffect: d — d (executing) d — (compiling)

Attributes: I

Description: If compiling, compile a stack double number into a literal. Later execution of the definition containing the literal will push it to the stack. If executing in ciforth, the number will just remain on the stack.

See also: ‘**LITERAL**’ ‘**LIT**’

8.2.2 LITERAL

Name: LITERAL

Stackeffect: $n - n$ (executing) $n -$ (compiling)

Attributes: ISO,I,C

Description: If compiling, then compile the stack value ‘ n ’ as a 64 bit literal. The intended use is: ‘: xxx [calculate] LITERAL ;’ Compilation is suspended for the compile time calculation of a value. Compilation is resumed and LITERAL compiles this value. Later execution of the definition containing the literal will push it to the stack. If executing in ciforth, the number will just remain on the stack.

See also: ‘LIT’ ‘LITERAL’

8.2.3 POSTPONE

Name: POSTPONE

No stackeffect

Attributes: ISO,I,C

Description: Used in a colon-definition in the form:

```
:  $xxx$  POSTPONE SOME-WORD
```

POSTPONE will postpone the compilation behaviour of ‘SOME-WORD’ to the definition being compiled. If ‘SOME-WORD’ is an immediate word this is similar to ‘[COMPILE] SOME-WORD’.

See also: ‘[COMPILE]’

8.2.4 [COMPILE]

Name: [COMPILE]

No stackeffect

Attributes: ISO,I,C

Description: Used in a colon-definition in the form:

```
:  $xxx$  ... [COMPILE] IF ... ;
```

[COMPILE] will force the compilation of an immediate definition, that would otherwise execute during compilation. The above example will perform IF when ‘ xxx ’ executes, rather than introducing conditional code in ‘ xxx ’ itself.

See also: ‘POSTPONE’

8.2.5 LIT

Name: LIT

Stackeffect: $- n$

Attributes: FIG,C

Description: Within a colon-definition, LIT is compiled followed by a 64 bit literal number given during compilation. Later execution of LIT causes the contents of this next dictionary cell to be pushed to the stack.

See also: ‘LITERAL’

8.2.6 SDLITERAL

Name: **SDLITERAL**

Stackeffect: d — s/d (executing) d — (compiling)

Attributes: I

Description: If compiling, compile a stack double number into a literal or double literal, depending on whether DPL contains a *nil pointer* or points into the input. Later execution of the definition containing the literal will push it to the stack. If executing, the number will remain on the stack.

See also: ‘SLITERAL’ ‘DLITERAL’

8.3 CONTROL

The wordset ‘CONTROL’ contains words that influence the control flow of a program, i.e. the sequence in which commands are executed in compiled words. With control words you can have actions performed repeatedly, or depending on conditions.

8.3.1 +LOOP

Name: **+LOOP**

Stackeffect: n1 — (run) addr n2 — (compile)

Attributes: ISO,I,C

Description: Used in a colon-definition in the form:

```
DO ... n1 +LOOP
```

At run-time, **+LOOP** selectively controls branching back to the corresponding **DO** based on ‘n1’, the loop index and the loop limit. The signed increment ‘n1’ is added to the index and the total compared to the limit. The branch back to **DO** occurs until the new index is equal to or greater than the limit (‘n1>0’), or until the new index is equal to or less than the limit (‘n1<0’). Upon exiting the loop, the parameters are discarded and execution continues ahead.

At compile time, **+LOOP** compiles the run-time word (**+LOOP**) and the branch offset computed from **HERE** to the address left on the stack by **DO**. ‘n2’ is used for compile time error checking.

8.3.2 ?DO

Name: **?DO**

Stackeffect: n1 n2 — (execute) addr n — (compile)

Attributes: NISO,I,C

Description: Occurs in a colon-definition in form:

```
?DO ... LOOP
```

It behaves like **DO**, with the exception that if ‘n1’ is less or equal to ‘n2’ the loop body is not executed. This is intended to suppress the unwanted behaviour of looping through the whole number range. ciforth deviates from ISO in that it also suppresses the unwanted behaviour of looping through almost the whole number range for an input of e.g.

```
1 2
```

```
.
```

See also: ‘DO’ ‘I’ ‘LOOP’ ‘+LOOP’ ‘LEAVE’

8.3.3 AGAIN

Name: **AGAIN**

Stackeffect: addr n — (compiling)

Attributes: ISO,FIG,I,C

Description: Used in a colon-definition in the form:

```
BEGIN ... AGAIN
```

At run-time, **AGAIN** forces execution to return to the corresponding **BEGIN** . There is no effect on the stack. Execution cannot leave this loop except for **EXIT** . At compile time, **AGAIN** compiles **BRANCH** with an offset from **HERE** to addr. ‘n’ is used for compile-time error checking.

See also: ‘**BEGIN**’

8.3.4 BEGIN

Name: **BEGIN**

Stackeffect: — addr n (compiling)

Attributes: ISO,FIG,I

Description: Occurs in a colon-definition in one of the forms:

```
BEGIN ... UNTIL
```

```
BEGIN ... AGAIN
```

```
BEGIN ... WHILE ... REPEAT
```

At run-time, **BEGIN** marks the start of a sequence that may be repetitively executed. It serves as a return point from the corresponding **UNTIL** , **AGAIN** or **REPEAT** . When executing **UNTIL** a return to **BEGIN** will occur if the top of the stack is false; for **AGAIN** and **REPEAT** a return to **BEGIN** always occurs.

At compile time **BEGIN** leaves its return address and ‘n’ for compiler error checking.

See also: ‘(BACK)’

8.3.5 CO

Name: **CO**

No stackeffect

Attributes:

Description: Return to the caller, suspending interpretation of the current definition, such that when the caller exits, this definition is resumed. The return stack must not be engaged, such as between **>R** and **R>** , or **DO** and **LOOP** .

See also: ‘**EXIT**’

8.3.6 DO

Name: **DO**

Stackeffect: n1 n2 — (execute) addr n — (compile)

Attributes: ISO,FIG,I,C

Description: Occurs in a colon-definition in form: ‘**DO ... LOOP**’ At run time, **DO** begins a sequence with repetitive execution controlled by a loop limit ‘n1’ and an index with initial value ‘n2’ . **DO** removes these from the stack. Upon reaching **LOOP** the index is incremented by

one. Until the new index equals or exceeds the limit, execution loops back to just after `DO` ; otherwise the loop parameters are discarded and execution continues ahead. Both `'n1'` and `'n2'` are determined at run-time and may be the result of other operations. Within a loop `I` will copy the current value of the index to the stack.

When compiling within the colon definition, `DO` compiles `(DO)` and leaves the following address `'addr'` and `'n'` for later error checking.

See also: `'I'` `'LOOP'` `'+LOOP'` `'LEAVE'`

8.3.7 ELSE

Name: `ELSE`

Stackeffect: `addr1 n1 — addr2 n2` (compiling)

Attributes: `ISO,FIG,I,C`

Description: Occurs within a colon-definition in the form:

```
IF ... ELSE ... THEN
```

At run-time, `ELSE` executes after the true part following `IF` . `ELSE` forces execution to skip over the following false part and resumes execution after the `THEN` . It has no stack effect.

At compile-time `ELSE` emplaces `BRANCH` reserving a branch offset, leaves the address `'addr2'` and `'n2'` for error testing. `ELSE` also resolves the pending forward branch from `IF` by calculating the offset from `'addr1'` to `HERE` and storing at `'addr1'` .

See also: `'(FORWARD'`

8.3.8 EXIT

Name: `EXIT`

No stackeffect

Attributes: `ISO`

Description: Stop interpretation of the current definition. The return stack must not be engaged, such as between `>R` and `R>` , or `DO` and `LOOP` . In ciforth it can also be used to terminate interpretation from a string, block or file, or a line from the current input stream.

See also: `'(;)'`

8.3.9 IF

Name: `IF`

Stackeffect: `f — (run-time) / — addr n` (compile)

Attributes: `ISO,FIG,I,C`

Description: Occurs in a colon-definition in form:

```
IF (tp) ... THEN
```

or

```
IF (tp) ... ELSE (fp) ... THEN
```

At run-time, `IF` selects execution based on a boolean flag. If `'f'` is true (non-zero), execution continues ahead thru the true part. If `'f'` is false (zero), execution skips till just after `ELSE` to execute the false part. After either part, execution resumes after `THEN` . `ELSE` and its false part are optional; if missing, false execution skips to just after `THEN` .

At compile-time `IF` compiles `OBRANCH` and reserves space for an offset at `'addr'` . `'addr'` and `'n'` are used later for resolution of the offset and error testing.

See also: `'(FORWARD'`

8.3.10 I

Name: I

Stackeffect: — n

Attributes: ISO,FIG,C

Description: Used within a do-loop to copy the loop index to the stack.

See also: 'DO' 'LOOP' '+LOOP'

8.3.11 J

Name: J

Stackeffect: — n

Attributes: ISO,FIG,C

Description: Used within a nested do-loop to copy the loop index of the outer do-loop to the stack.

See also: 'DO' 'LOOP' '+LOOP'

8.3.12 LEAVE

Name: LEAVE

No stackeffect

Attributes: ISO

Description: Terminate a do-loop by branching to directly behind the end of a loop started by DO or ?DO , so after the corresponding LOOP or +LOOP .

8.3.13 LOOP

Name: LOOP

Stackeffect: — (run) addr n — (compiling)

Attributes: ISO,I,C

Description: Occurs in a colon-definition in form:

```
DO ... LOOP
```

At run-time, LOOP selectively controls branching back to the corresponding DO based on the loop index and limit. The loop index is incremented by one and compared to the limit. The branch back to DO occurs until the index equals or exceeds the limit; at that time, the parameters are discarded and execution continues ahead.

At compile-time, LOOP compiles (+LOOP) and uses 'addr' to calculate an offset to 'DO' . 'n2' is used for compile time error checking.

See also: '+LOOP'

8.3.14 RECURSE

Name: RECURSE

Stackeffect: (varies)

Attributes: ISO

Description: Do a recursive call of the definition being compiled.

See also: ':'

8.3.15 REPEAT

Name: REPEAT

Stackeffect: addr1 n1 addr2 n2— (compiling)

Attributes: ISO,FIG,I,C

Description: Used within a colon-definition in the form:

```
BEGIN ... WHILE ... REPEAT
```

At run-time, REPEAT forces an unconditional branch back to just after the corresponding BEGIN .

At compile-time, REPEAT compiles BRANCH and the offset from HERE to ‘addr2’ . Then it fills in another branch offset at ‘addr1’ left there by WHILE . ‘n1 n2’ is used for error testing.

See also: ‘WHILE’

8.3.16 SKIP

Name: SKIP

No stackeffect

Attributes: C

Description: Skip over an area in memory, where the length is given in the next cell, then align. This length doesn’t include the length cell, so it is compatible with \$@ . Internal, used for nested compilation and compiling strings.

See also: ‘BRANCH’

8.3.17 THEN

Name: THEN

Stackeffect: addr n — (compile)

Attributes: ISO,FIG,I,C

Description: Occurs in a colon-definition in form:

```
IF ... THEN
```

```
IF ... ELSE ... THEN
```

At run-time, THEN serves only as the destination of a forward branch from IF or ELSE . It marks the conclusion of the conditional structure. At compile-time, THEN computes the forward branch offset from ‘addr’ to HERE and stores it at ‘addr’ . ‘n’ is used for error tests.

See also: ‘FORWARD’) ‘IF’ ‘ELSE’

8.3.18 UNLOOP

Name: UNLOOP

No stackeffect

Attributes: ISO,I,C

Description: Discard the loop parameters. Must be used when the regular end of the loop is by-passed. That means it is not ended via LOOP +LOOP or LEAVE .

See also: ‘DO’ ‘LOOP’ ‘+LOOP’ ‘(BACK’ ‘(FORWARD’ ‘EXIT’

8.3.19 UNTIL

Name: UNTIL

Stackeffect: f — (run-time) addr n — (compile)

Attributes: ISO,FIG,I,C

Description: Occurs within a colon-definition in the form:

```
BEGIN ... UNTIL
```

At run-time, UNTIL controls the conditional branch back to the corresponding BEGIN. If f is false, execution returns to just after BEGIN, otherwise execution continues ahead.

At compile-time, UNTIL compiles OBRANCH and an offset from HERE to addr. ' n ' is used for error tests.

See also: 'BEGIN'

8.3.20 WHILE

Name: WHILE

Stackeffect: f — (run-time) addr1 $n1$ — addr2 $n1$ addr1 $n2$ (compile-time)

Attributes: ISO,FIG,I,C

Description: Occurs in a colon-definition in the form: 'BEGIN ... WHILE (tp) ... REPEAT'. At run-time, WHILE selects conditional execution based on boolean flag ' f '. If ' f ' is true (non-zero), WHILE continues execution of the true part thru to REPEAT, which then branches back to BEGIN. If ' f ' is false (zero), execution skips to just after REPEAT, exiting the structure.

At compile time, WHILE compiles OBRANCH and tucks the target address ' $addr2$ ' under the ' $addr1$ ' left there by BEGIN. The stack values will be resolved by REPEAT. ' $n1$ ' and ' $n2$ ' provide checks for compiler security.

See also: '(FORWARD)' 'BEGIN'

8.3.21 (+LOOP)

Name: (+LOOP)

Stackeffect: n —

Attributes: C

Description: The run-time procedure compiled by +LOOP, which increments the loop index by n and tests for loop completion.

See also: '+LOOP'

8.3.22 (;)

Name: (;)

No stackeffect

Attributes:

Description: This is a synonym for EXIT. It is the run-time word compiled at the end of a colon-definition which returns execution to the calling procedure. Stop interpretation of the current definition. The return stack must not be engaged.

See also: 'EXIT'

8.3.23 (?DO)

Name: (?DO)

No stackeffect

Attributes: C

Description: The run-time procedure compiled by ?DO which prepares the return stack, where the looping bookkeeping is kept.

See also: 'DO'

8.3.24 (BACK

Name: (BACK

Stackeffect: — addr

Attributes:

Description: Start a backward branch by leaving the target address HERE into 'addr'. Usage is '(BACK .. POSTPONE BRANCH BACK) '

See also: 'BACK)' 'BEGIN' 'DO'

8.3.25 (DO)

Name: (DO)

No stackeffect

Attributes: C

Description: The run-time procedure compiled by DO which prepares the return stack, where the looping bookkeeping is kept.

See also: 'DO'

8.3.26 (FORWARD

Name: (FORWARD

Stackeffect: — addr

Attributes:

Description: Start a forward branch by leaving the address that must be backpatched with an offset into 'addr'. Usage is 'POSTPONE BRANCH (FORWARD .. FORWARD) '

See also: 'IF'

8.3.27 0BRANCH

Name: 0BRANCH

Stackeffect: f —

Attributes: FIG,C

Description: The run-time procedure to conditionally branch. If 'f' is false (zero), the following in-line parameter is added to the interpretive pointer to branch ahead or back. Compiled by IF , UNTIL , and WHILE .

See also: 'BRANCH' 'FORWARD' 'BACK) '

8.3.28 BACK)

Name: BACK)

Stackeffect: addr —

Attributes:

Description: Complete a backward branch by compiling an offset from **HERE** to ‘**addr**’, left there by (**BACK** . Usage is ‘(**BACK** .. **POSTPONE BRANCH BACK**) ’

See also: ‘**LOOP**’ ‘**UNTIL**’

8.3.29 **BRANCH**

Name: **BRANCH**

No stackeffect

Attributes: **FIG,C**

Description: The run-time procedure to unconditionally branch. An in-line offset is added to the interpretive pointer **IP** to branch ahead or back. **BRANCH** is compiled by **ELSE AGAIN REPEAT** .

See also: ‘**OBRANCH**’ ‘**FORWARD**’ ‘**BACK**) ’

8.3.30 **FORWARD)**

Name: **FORWARD)**

Stackeffect: **addr** —

Attributes:

Description: Complete a forward branch by backpatching an offset from **HERE** into ‘**addr**’, left there by (**FORWARD** . Usage is ‘**POSTPONE BRANCH (FORWARD** .. **FORWARD)** ’

See also: ‘**LOOP**’ ‘**UNTIL**’

8.4 **DEFINING**

The wordset ‘**DEFINING**’ contains words that add new entries to the dictionary. A number of such *defining word* ’s are predefined, but there is also the possibility to make new defining words, using **CREATE** and **DOES>** .

8.4.1 **;**

Name: **;**

No stackeffect

Attributes: **ISO,FIG,I,C**

Description: Terminate a colon-definition and stop further compilation. Compiles the run-time (**;**) .

See also: ‘**:**’

8.4.2 **CONSTANT**

Name: **CONSTANT**

Stackeffect: **n** —

Attributes: **ISO,FIG**

Description: A defining word used in the form: ‘**n**’ **CONSTANT** ‘**cccc**’ to create word ‘**cccc**’ , where the content of its *data field address* is ‘**n**’ . When ‘**cccc**’ is later executed, it will push the value of ‘**n**’ to the stack.

See also: ‘**VARIABLE**’ ‘**>DFA**’

8.4.3 CREATE

Name: **CREATE**

No stackeffect

Attributes: ISO

Description: A defining word used in the form: `'CREATE cccc'` Later execution of `'cccc'` returns its *data* field, i.e. the value of **HERE** immediately after executing **CREATE** .

It can be the base of a new defining word if used in the form:

```
: CREATOR CREATE aaaa DOES> bbbb ;
CREATOR cccc
```

The second line has the effect of creating a word `'cccc'` . Its datastructure is build by the code `'aaaa'` and when executing `'cccc'` , its data field is pushed on the stack, then the code `'bbbb'` is executed.

Space in this data field has yet to be allocated and the execution action can be changed. ciforth is byte aligned, so no extra measures are needed.

See also: `'>BODY'` `'DOES>'` `' ;CODE'` `'ALLOT'` `' , '`

8.4.4 DATA

Name: **DATA**

No stackeffect

Attributes:

Description: A defining word used in the form: `'DATA cccc'` When **DATA** is executed, it creates the definition `'cccc'` whose *data field address* contains a pointer `'n'` to **HERE** . This code is typically followed by some data allocation word like **ALLOT** or `' , . DOES>` must not be used with `'cccc'`.

When `'cccc'` is later executed, this pointer `'n'` is left on the stack, so that data can be accessed.

See also: `'VARIABLE'` `'CREATE'` `'>DFA'`

8.4.5 DOES>

Name: **DOES>**

No stackeffect

Attributes: ISO,FIG

Description: A word which is used in combination with **CREATE**

to specify the run-time action within a high-level defining word. **DOES>** modifies the default behaviour of the created word so as to execute the sequence of compiled word addresses following **DOES>** . When the **DOES>** part executes it begins with the address of the data field of the word on the stack. This allows interpretation using this area or its contents. Typical uses include the Forth assembler, arrays and matrices, and compiler generation.

8.4.6 MAX-USER

Name: **MAX-USER**

Stackeffect: — addr

Attributes: U

Description: A user variable which contains the offset of next user variable. It is measured in cells from the start of the user area.

See also: `'BLOCK'` `'USER'` `'MESSAGE'` `'UO'`

8.4.7 NAMESPACE

Name: NAMESPACE

No stackeffect

Attributes:

Description: A defining word used in the form: NAMESPACE ‘cccc’ to create a namespace definition ‘cccc’ . It will create a *word list* in the ISO sense. Subsequent use of ‘cccc’ will push this word list (the *word list associated with ‘cccc’*) to the top of the search order in CONTEXT . So it will be searched first by INTERPRET .

A namespace’s data content field contains at first the dovoc pointer (like for any DOES> word) , then follows its body. The body contains the namespace ("vocabulary") link field address (VLFA). The VLFA points to the VLFA of the next namespace or a *nil pointer* for the end. Then follows a dummy dea that serves as *word list identifier* or WID in the sense of the ISO standard. It has empty fields, except for the link field. The *link field address* contains the DEA of the latest word of the namespace or a *nil pointer* if empty. Executing the namespace means pushing its WID on top of the CONTEXT order. In ciforth when there can be at most 16 word list’s in the search order, the oldest one gets lost. The vocabularies generated are IMMEDIATE words.

See also: ‘VOC-LINK’ ‘DEFINITIONS’ ‘FOR-VOCS’ ‘>WID’

8.4.8 USER

Name: USER

Stackeffect: n —

Attributes: ISO

Description: A defining word used in the form: ‘n USER cccc’ which creates a user variable ‘cccc’ . The data field of ‘cccc’ contains ‘n’ as a cell offset relative to the user pointer register ‘UP’ for this user variable. When ‘cccc’ is later executed, it places the sum of its offset and the user area base address on the stack as the storage address of that particular variable. In this ciforth the ‘UP’ is to be found at ‘0 +ORIGIN’.

CONTEXT is the last user variable at offset M4_USUSED , such that new user variables may be allocated using offsets of M4_USUSED+16 and up.

See also: ‘VARIABLE’ ‘+ORIGIN’ ‘CONTEXT’ ‘>DFA’

8.4.9 VARIABLE

Name: VARIABLE

No stackeffect

Attributes: ISO,FIG

Description: A defining word used in the form: ‘VARIABLE cccc’ When VARIABLE is executed, it creates the definition ‘cccc’ whose *data field address* contains a pointer ‘n’ to a data location. When ‘cccc’ is later executed, this pointer ‘n’ is left on the stack, so that a fetch or store may access this location.

See also: ‘USER’ ‘CONSTANT’ ‘>DFA’

8.4.10 WORDLIST

Name: WORDLIST

Stackeffect: — wid

Attributes: ISO

Description: This words creates an empty wordlist which is a single header structure *dea* that serves as a *word list identifier* or WID in the sense of the ISO standard. Definitions will be

added to it after it has been copied to **CURRENT** . This handle can be placed in the top of the search order **CONTEXT** and the wordlist will be searched. This word underlies **NAMESPACE** , there is no **VLFA** .

A wid's significant fields are the flag field and the link field. The flag field indicates that it is dummy, i.e. not intended to be executed. The *link field address* contains the *dea* of the latest word of the wordlist or a *nil pointer* if empty. The namefield points to an empty string

See also: 'NAMESPACE' 'ALSO' '>FFA' '>LFA' 'FOR-WORDS'

8.4.11 colon

Name: colon

No stackeffect

Attributes: ISO,FIG,E

Description: Used in the form called a colon-definition:

```
: cccc      ...      ;
```

Creates a dictionary entry defining 'cccc' as equivalent to the following sequence of Forth word definitions '...' until the next ';' or ';'CODE' . The word is added as the latest into the **CURRENT** word list. The compiling process is done by the text interpreter as long as **STATE** is non-zero. Words with the immediate bit set (I) are executed rather than being compiled.

See also: '(CREATE)'

8.4.12 (;CODE)

Name: (;CODE)

No stackeffect

Attributes: WANT,C

Description: The run-time procedure, compiled by ;CODE , that rewrites the code field of the most recently defined word to point to the following machine code sequence. It is used after **CREATE** instead of **DOES>** if the code following is assembler code instead of high level code.

See also: ' ;CODE'

8.4.13 (CREATE)

Name: (CREATE)

Stackeffect: sc —

Attributes:

Description: This is the basis for all defining words, including those which lack a data field in the ISO sense: : **USER VARIABLE NAMESPACE CONSTANT** . It creates a header with name 'sc' in the dictionary and links it into the **CURRENT** word list.

See also: 'HEADER' 'LINK' 'CREATE'

8.4.14 ;CODE

Name: ;CODE

No stackeffect

Attributes: WANT,ISO,FIG,I,C

Description: Used in the form: ': cccc **CREATE** ;CODE **assembly mnemonics** ' Stop compilation and terminate a new defining word 'cccc' by compiling (;CODE) . Set **ASSEMBLER** to the top of the *search order* order. Start assembling to machine code the following mnemonics.

When ‘cccc’ later executes in the form: ‘cccc nnnn’ the word ‘nnnn’ will be created with its execution procedure given by the machine code following ‘cccc’ . That is, when ‘nnnn’ is executed, it does so by jumping to the code after ‘nnnn’ . Because of intimate relation to the assembler, it is present in loadable form in the screens file `forth.lab` .

See also: ‘(;CODE)’ ‘(CREATE)’

8.4.15 HEADER

Name: HEADER

Stackeffect: sc — dea

Attributes:

Description: Create a dictionary entry structure for the word ‘sc’ and returns its address into ‘dea’. A pointer to each of its fields is called a "field address". In particular that a data field address is not a *data field*

in the ISO sense. The *code field address* and *data field address* addres contain a same pointer, to the area owned by this header, i.e. immediately following the completed header as appropriate for a low level (assembler) definition. The flag and link fields are initialised to zero , so not HIDDEN . The name ‘sc’ is layed down in the dictionary before the header and filled in into the name field. The source field is filled in to best knowledge.

See also: ‘(CREATE)’ ‘LINK’ ‘>CFA’ ‘>DFA’ ‘>FFA’ ‘>LFA’ ‘>NFA’ ‘>SFA’ ‘>XFA’

8.4.16 LINK

Name: LINK

Stackeffect: dea wid —

Attributes:

Description: Links the Forth word represented by ‘dea’ into the wordlist represented by ‘wid’ as the latest entry. Alternatively, consider ‘wid’ as an other ‘dea2’. Link ‘dea’ between the ‘dea2’ and its successor in the linked list.

See also: ‘HEADER’ ‘(CREATE)’

8.5 DENOTATIONS

The wordset ‘DENOTATIONS’ contains prefixes (mostly one letter words) that introduce a *denotation* , i.e. a generalisation of NUMBER . PREFIX turns the latest definition into a prefix, similar to IMMEDIATE . If a word starting with the prefix is looked up in the dictionary, the prefix is found and executed. Prefix words parse input and leave a constant (number, char or string) on the stack, or compile such constant, depending on STATE . For a kernel system it is guaranteed that they reside in the minimum search order wordlist, associated with the namespace ONLY . To make a distinction with the same words in other wordlists, the names of denotations are prepended with “Prefix_” in the documentation. Actual names consists of the one character following “Prefix”. Apart from Prefix_0 , ONLY

contains entries for all hex digits 1...9 and A...F. Like NUMBER always did, all denotations behave identical in interpret and compile mode and they are not supposed to be postponed.

8.5.1 Prefix_"

Name: Prefix_"

Stackeffect: — sc

Attributes: C,I

Description: Parse a " delimited string and leave it on the stack. A " can be embedded in a string by doubling it. The string is permanent and takes dictionary space. This is a denotation: during compilation this behaviour is compiled.

8.5.2 Prefix_&

Name: `Prefix_&`

Stackeffect: — c

Attributes: C,I

Description: Leave ‘c’ the non blank char that follows. Skip another blank character. This is a denotation: during compilation this behaviour is compiled.

See also: ‘^’

8.5.3 Prefix_+

Name: `Prefix_+`

Stackeffect: — s/d

Attributes: I,P

Description: A prefix that handles numbers that start with + .

See also: ‘NUMBER’ ‘7’ ‘B’

8.5.4 Prefix_-

Name: `Prefix_-`

Stackeffect: — s/d

Attributes: I,P

Description: A prefix that handles numbers that start with - .

See also: ‘NUMBER’ ‘7’ ‘B’

8.5.5 Prefix_0

Name: `Prefix_0`

Stackeffect: — s/d

Attributes: C,I

Description: A prefix that handles numbers that start with 0 . Similar words are present for all decimal and hex digits. ISO compatibility only requires that denotators for decimal digits are present, one can always use a leading zero.

See also: ‘NUMBER’ ‘B’ ‘7’

8.5.6 Prefix_7

Name: `Prefix_7`

Stackeffect: — s/d

Attributes: C,I

Description: Implements NUMBER for numbers that start with 7 . Similar words are present for all decimal and hex digits.

See also: ‘NUMBER’ ‘O’ ‘B’

8.5.7 Prefix_B

Name: `Prefix_B`

Stackeffect: — s/d

Attributes: C,I

Description: Implements NUMBER for numbers that start with B . Similar words are present for all decimal and hex digits.

See also: ‘O’ ‘7’

8.5.8 Prefix_TICK

Name: `Prefix_TICK`

Stackeffect: — addr

Attributes: ISO,FIG,C,I

Description: Used in the form:

`'nnnn`

In interpret mode it leaves the *execution token*

(equivalent to the *dea* dictionary entry address) of dictionary word `'nnnn'`. If the word is not found after a search of the search order an appropriate error message is given. In compile mode it finds the same address, then compiles it as a literal. It is recommended that one never compiles or postpones it. (Use a combination of `NAME` and `FOUND` or any form of explicit parsing and searching instead.) Furthermore it is recommended that for non-portable code `'` is used in its *denotation* form without the space. Note that if you separate `'` by a space, the ISO-conforming version of `'` is found.

See also: `'HEADER'` `'CONTEXT'` `'[']` `'PRESENT'` `'>CFA'` `'>DFA'` `'>FFA'` `'>LFA'` `'>NFA'`

8.5.9 Prefix_^

Name: `Prefix_^`

Stackeffect: — b

Attributes: C,I

Description: Leave `'b'` the control character value of the char that follows i.e. `'^A'` results in 1 and so on. Skip another blank character. This is a denotation: during compilation this behaviour is compiled.

See also: `'&'`

8.6 DICTIONARY

The wordset `'DICTIONARY'` contains words that at a lower level than the wordset `'DEFINING'` concern the memory area that is allocated to the dictionary. They may add data to the dictionary at the expense of the free space, one cell or one byte at a time, or allocate a buffer at once. The dictionary space may also be shrunk, and the words that were there are lost. The *dictionary entry address* or *DEA* represents a word. It is the lowest address of a record with fields. Words to access those fields also belong to this wordset.

8.6.1 `'` (This addition because texinfo won't accept a single quote)

Name: `'`

Stackeffect: — addr

Attributes: ISO,FIG,I

Description: Used in the form:

`' nnnn`

It leaves the *execution token* (equivalent to the dictionary entry address) of dictionary word `'nnnn'`. If the word is not found after a search of the search order an appropriate error message is given. If compiled the searching is done while the word being compiled is executed. Because this is so confusing, it is recommended that one never compiles or postpones `'`. (Use a combination of `WORD` and `FIND` or any form of explicit parsing and searching instead.) Furthermore it is recommended that for non-portable code `'` is used in its *denotation* form without the space.

See also: `'[']` `'FOUND'` `'>CFA'` `'>DFA'` `'>FFA'` `'>LFA'` `'>NFA'` `'>SFA'` `'>XFA'`

8.6.2 ,

Name: ,

Stackeffect: n —

Attributes: ISO,FIG

Description: Store ‘n’ into the next available dictionary memory cell, advancing the *dictionary pointer* .

See also: ‘DP’ ‘C,’

8.6.3 2,

Name: 2,

Stackeffect: d —

Attributes: ISO,FIG

Description: Store the most significant cell of ‘d’ into the next available dictionary cell, advancing the *dictionary pointer* , then the least significant one. .

See also: ‘DP’ ‘,’

8.6.4 >BODY

Name: >BODY

Stackeffect: dea — addr

Attributes: ISO

Description: Given the *dictionary entry address* ‘dea’ of a definition created with a **CREATE / DOES>** construct, return its *data field* (in the ISO sense) ‘addr’.

See also: ‘,’ ‘>CFA’ ‘>DFA’ ‘>PHA’ ‘BODY>’

8.6.5 ALLOT

Name: ALLOT

Stackeffect: n —

Attributes: ISO,FIG

Description: Add the signed number to the *dictionary pointer* DP . May be used to reserve dictionary space or re-origin memory. As the Pentium is a byte-addressable machine ‘n’ counts bytes.

See also: ‘HERE’ ‘,’

8.6.6 BODY>

Name: BODY>

Stackeffect: addr — dea

Attributes:

Description: Convert the data field ‘addr’ of a definition created with a **CREATE / DOES>** construct (this is not a header *data field address*) to its ‘dea’. Where >BODY keeps working after *revectoring* , BODY> does not. There is some logic to this, because the *DEA* to which the body belongs is no longer unique.

See also: ‘,’ ‘>BODY’

8.6.7 C,

Name: C,

Stackeffect: b —

Attributes: ISO,FIG

Description: Store 8 bits of ‘b’ into the next available dictionary byte, advancing the *dictionary pointer* .

See also: ‘DP’ ‘,’

8.6.8 DP

Name: DP

Stackeffect: — addr

Attributes: FIG,U,L

Description: A user variable, the *dictionary pointer* , which contains the address of the next free memory above the dictionary. The value may be read by **HERE** and altered by **ALLOT** .

8.6.9 FIND

Name: FIND

Stackeffect: addr —xt 1/xt -1/addr 0

Attributes: ISO,WANT

Description: For the *old fashioned string* (stored with a preceding character count) at ‘addr’ find a Forth word in the current search order. Return its execution token ‘xt’. If the word is immediate, also return 1, otherwise also return -1. If it is not found, leave the original ‘addr’ and a zero. In ciforth the alternative **FOUND** is used, that uses a regular string.

See also: ‘CONTEXT’ ‘PRESENT’ ‘(FIND)’

8.6.10 FORGET

Name: FORGET

No stackeffect

Attributes: ISO,FIG,E

Description: Executed in the form: **FORGET** ‘cccc’ Deletes definition named ‘cccc’ from the dictionary with all entries physically following it. Recover the space that was in use.

See also: ‘FENCE’ ‘FORGET-VOC’

8.6.11 FOUND

Name: FOUND

Stackeffect: sc — dea

Attributes:

Description: Look up the string ‘sc’ in the dictionary observing the current search order. If found, leave the dictionary entry address ‘dea’ of the first entry found, else leave a *nil pointer*. If the first part of the string matches a *denotation* word, that word is found, whether the denotation is correct or not.

See also: ‘PRESENT’ ‘CONTEXT’ ‘(FIND)’ ‘PREFIX’ ‘FIND’

8.6.12 HERE

Name: HERE

Stackeffect: — addr

Attributes: ISO,FIG

Description: Leave the address ‘addr’ of the next available dictionary location.

See also: ‘DP’

8.6.13 ID.

Name: ID.

Stackeffect: dea —

Attributes:

Description: Print a definition’s name from its dictionary entry address. For dummy entries print nothing.

See also: ‘,’ ‘>FFA’ ‘>NFA’

8.6.14 IMMEDIATE

Name: IMMEDIATE

No stackeffect

Attributes:

Description: Mark the most recently made definition so that when encountered at compile time, it will be executed rather than being compiled, i.e. the immediate bit in its header is set. This method allows definitions to handle special compiling situations, rather than build them into the fundamental compiler. The user may force compilation of an immediate definition by preceding it with POSTPONE .

8.6.15 PAD

Name: PAD

Stackeffect: — addr

Attributes: ISO,FIG

Description: Leave the address of the text output buffer, which is a fixed offset above HERE . The area growing downward from PAD is used for numeric conversion.

8.6.16 PREFIX

Name: PREFIX

No stackeffect

Attributes:

Description: Mark the most recently made definition a *prefix* . If searching the wordlists for a name that starts with the prefix, the prefix is a match for that name. This method allows to define numbers, and other *denotations* such as strings, in a modular and extensible fashion. A prefix word finds the interpreter pointer pointing to the remainder of the name (or number) sought for, and must compile that remainder. Prefix words are mostly both immediate and *smart* , i.e. they behave differently when compiled, than interpreted. The result is that the compiled code looks the same and behaves the same than the interpreted code. It is recommended that the only smart words present are prefix words.

See also: ‘PP@@’ ‘IMMEDIATE’ ‘Prefix_0’

8.6.17 PRESENT

Name: PRESENT

Stackeffect: sc — dea

Attributes:

Description: If the string ‘sc’ is present as a word name in the current search order, return its ‘dea’, else leave a *nil pointer* . For a *denotation* word, the name must match ‘sc’ exactly.

See also: ‘FOUND’ ‘CONTEXT’ ‘(FIND)’ ‘NAMESPACE’ ‘FIND’

8.6.18 WORDS

Name: WORDS

No stackeffect

Attributes: ISO

Description: List the names of the definitions in the topmost word list of the search order. Contrary to custom the most recent words is shown last.

See also: ‘CONTEXT’

8.6.19 [’]

Name: [’]

Stackeffect: — addr

Attributes: ISO,I

Description: Used in the form:

[’] nnnn

In compilation mode it leaves the *execution token* (equivalent to the dictionary entry address) of dictionary word ‘nnnn’. So as a compiler directive it compiles the address as a literal. If the word is not found after a search of the search order an appropriate error message is given. It is recommended that where you can’t use a *denotation* , or don’t want to, you use a combination of NAME and FOUND (or WORD and FIND) instead.

See also: ‘FOUND’ ‘,’ ‘EXECUTE’

8.6.20 (FIND)

Name: (FIND)

Stackeffect: sc wid — sc dea

Attributes:

Description: Search down from the WID ‘wid’ for a word with name ‘sc’. A WID is mostly a dummy DEA found in the data field of a namespace, fetched from CURRENT or an other wid in the *search order* . Leave the dictionary entry address ‘dea’ of the first entry found, else leave a zero. Do not consume the string ‘sc’, as this is a repetitive action.

See also: ‘~MATCH’ ‘FOUND’ ‘PRESENT’ ‘>WID’

8.6.21 >CFA

Name: >CFA

Stackeffect: dea — addr

Attributes:

Description: Given a dictionary entry address ‘dea’ return its *code field address* ‘addr’. By jumping indirectly via this address the definition ‘dea’ is executed. This is the address that is

compiled within high level definitions, so it serves as an execution token. In ciforth it has offset 0, so it is actually the same as the *DEA* .

See also: ‘Prefix_’ ‘HEADER’

8.6.22 >DFA

Name: >DFA

Stackeffect: dea — addr

Attributes:

Description: Given a dictionary entry address return its *data field address* ‘addr’ . This points to the code for a code word, to the high level code for a colon-definition, and to the DOES> pointer for a word build using CREATE . Normally this is the area behind the header, found via >PHA .

See also: ‘Prefix_’ ‘>BODY’ ‘HEADER’

8.6.23 >FFA

Name: >FFA

Stackeffect: dea — addr

Attributes:

Description: Given a dictionary entry address return its *flag field address* ‘addr’ .

See also: ‘Prefix_’ ‘HEADER’ ‘IMMEDIATE’ ‘PREFIX’

8.6.24 >LFA

Name: >LFA

Stackeffect: dea — addr

Attributes:

Description: Given a dictionary entry address return its *link field address* ‘addr’ . It contains the DEA of the previous word.

See also: ‘Prefix_’ ‘HEADER’

8.6.25 >NFA

Name: >NFA

Stackeffect: dea — nfa

Attributes:

Description: Given a dictionary entry address return the *name field address* .

See also: ‘Prefix_’ ‘HEADER’ ‘ID.’

8.6.26 >PHA

Name: >PHA

Stackeffect: dea — addr

Attributes:

Description: Given a dictionary entry address return the *past header address* . Here starts the area that no longer belongs to the header of a dictionary entry, but most often it is owned by it.

See also: ‘Prefix_’ ‘HEADER’ ‘>BODY’

8.6.27 >SFA

Name: >SFA

Stackeffect: dea — addr

Attributes:

Description: Given a dictionary entry address return the *source field address* ‘addr’ .

See also: ‘Prefix_’ ‘HEADER’

8.6.28 >VFA

Name: >VFA

Stackeffect: dea — cfa

Attributes:

Description: Given the dictionary entry address of a namespace return the address of the link to the next namespace. Traditionally this was called vocabulary, hence the *V*.

See also: ‘NAMESPACE’ ‘>CFA’ ‘>WID’

8.6.29 >WID

Name: >WID

Stackeffect: dea — wid

Attributes:

Description: Given the dictionary entry address ‘dea’ of a namespace return its *WID* ‘wid’, a dummy DEA that serves as the start of a dictionary search.

See also: ‘NAMESPACE’ ‘>VFA’ ‘(FIND)’

8.6.30 FENCE

Name: FENCE

Stackeffect: — addr

Attributes: FIG,U

Description: A user variable containing an address below which FORGET ting is trapped. To forget below this point the user must alter the contents of FENCE .

8.6.31 FOR-VOCS

Name: FOR-VOCS

Stackeffect: x1..xn xt — x1...xn

Attributes:

Description: For all vocabularies execute ‘xt’ with as data the *DEA* of those words. ‘xt’ must have the stack diagram ‘x1..xn dea --- x1..xn’

See also: ‘FOR-WORDS’ ‘EXECUTE’

8.6.32 FOR-WORDS

Name: FOR-WORDS

Stackeffect: x1...xn xt wid — x1...xn

Attributes:

Description: For all words from a word list identified by ‘wid’ execute ‘xt’ with as data ‘x1..xn’ plus the *DEA* of those words. ‘xt’ must have the stack diagram ‘x1..xn dea --- x1..xn’. Note that you can use the DEA of any word as a WID and the remainder of the word list will be searched.

See also: ‘FOR-VOCS’ ‘EXECUTE’

8.6.33 FORGET-VOC

Name: FORGET-VOC

Stackeffect: addr wid — addr

Attributes:

Description: Remove all words whose DEA is greater (which mostly means later defined) than ‘addr’ from a wordlist given by ‘wid’ . This works too if links have been redirected, such that some earlier words point back to later defined words. Leave ‘addr’ (as FORGET-VOC is intended to be used with FOR-VOCS) . If any whole namespace is removed, the search order is reset to ‘ONLY FORTH’. The space freed is not recovered.

See also: ‘FORGET’

8.6.34 HIDDEN

Name: HIDDEN

Stackeffect: dea —

Attributes:

Description: Make the word with dictionary entry address ‘dea’ unfindable, by toggling the "smudge bit" in a definitions’ flag field. If however it was the ‘dea’ of an unfindable word, it is made findable again. Used during the definition of a colon word to prevents an uncompleted definition from being found during dictionary searches, until compiling is completed without error. It also prevents that a word can be used recursively.

See also: ‘IMMEDIATE’ ‘RECURSE’

8.6.35 ~MATCH

Name: ~MATCH

Stackeffect: sc dea — sc dea n

Attributes:

Description: Intended to cooperate with (FIND) . Compares the *string constant* ‘sc’ with the dea ‘dea’. Returns into ‘n’ the difference between the first characters that compare unequal, or zero if the strings are the same up to the smallest length. It is required that the dea has a non-zero name field.

See also: ‘FOUND’ ‘CORA’

8.7 DOUBLE

The wordset ‘DOUBLE’ contains words that manipulate *double* ’s.

8.7.1 D+

Name: D+

Stackeffect: d1 d2 — dsum

Attributes: ISO,FIG

Description: Leave the double number ‘dsum’: the sum of two double numbers ‘d1’ and ‘d2’ .

See also: ‘DNEGATE’ ‘+’

8.7.2 DABS

Name: DABS

Stackeffect: d — ud

Attributes: ISO,FIG

Description: Leave the absolute value ‘ud’ of a double number ‘d’ .

See also: ‘DNEGATE’ ‘ABS’

8.7.3 DNEGATE

Name: DNEGATE

Stackeffect: d1 — d2

Attributes: ISO

Description: ‘d2’ is the negation of ‘d1’.

See also: ‘D+’

8.7.4 S>D

Name: S>D

Stackeffect: n — d

Attributes: ISO

Description: Sign extend a single number to form a double number.

8.8 ENVIRONMENTS

The wordset ‘ENVIRONMENTS’ contains all words of the ENVIRONMENT namespace and those words needed to recognize them as Forth environment queries. Note that these are not environment variables in the sense that are passed from an operating system to a program.

8.8.1 CORE

Name: CORE

Stackeffect: — ff

Attributes: ISO

Description: An environment query whether the CORE wordset is present.

See also: ‘ENVIRONMENT?’

8.8.2 CPU

Name: CPU

Stackeffect: — d

Attributes: CI

Description: An environment query returning the cpu-type to be printed as a base-36 number.

See also: ‘ENVIRONMENT?’

8.8.3 ENVIRONMENT?

Name: ENVIRONMENT?

Stackeffect: sc — i*x true/false

Attributes: ISO

Description: If the string ‘sc’ is a known environment attribute, leave into ‘i*x’ the information about that attribute and a true flag, else leave a false flag. In fact the flag indicates whether the words is present in the ENVIRONMENT namespace and ‘i*x’ is what is left by the word if executed.

See also: ‘NAMESPACE’

8.8.4 NAME

Name: NAME

Stackeffect: — sc

Attributes: CI

Description: An environment query giving the name of this Forth as a *string constant*.

See also: ‘ENVIRONMENT?’

8.8.5 SUPPLIER

Name: SUPPLIER

Stackeffect: — sc

Attributes: CI

Description: An environment query giving the SUPPLIER of this Forth as a *string constant*.

See also: 'ENVIRONMENT?'

8.8.6 VERSION

Name: VERSION

Stackeffect: — sc

Attributes: CI

Description: An environment query giving the version of this Forth as a *string constant*.

See also: 'ENVIRONMENT?'

8.9 ERRORS

The wordset 'ERRORS' contains words to handle errors and exceptions.

8.9.1 ?ERROR

Name: ?ERROR

Stackeffect: f n —

Attributes:

Description:

If the boolean flag is true, *signal an error* with number 'n'. This means that an exception is thrown, and it is remembered that this is the original place where the exception originated. If the exception is never caught, an error message is displayed using **ERROR** . All errors signaled by the kernel go through this word.

See also: 'ERROR' '?ERRUR' 'THROW'

8.9.2 ?ERRUR

Name: ?ERRUR

Stackeffect: n —

Attributes:

Description: Handle the possible error 'n' in Unix fashion. If it is zero or positive, this means okay. If it is negative, its value identifies an error condition. This error is handled in the same way as by ?ERROR .

See also: 'ERROR' '?ERROR'

8.9.3 ABORT"

Name: ABORT"

Stackeffect: f —

Attributes: ISO,I,C

Description: Usage is ': <SOME> ... ABORT" <message>" ... ;'. If ABORT" finds a non-zero 'f' on the stack, the '<message>' is displayed and an ABORT is executed. Otherwise proceed with the words after '<message>'. This word can only be used in compile mode.

See also: '?ERROR'

8.9.4 CATCH

Name: **CATCH**

Stackeffect: ... **xt** — ... **tc**

Attributes: ISO

Description: Execute '**xt**'. If it executes successfully, i.e. no **THROW** is executed by '**xt**', leave a zero into '**tc**' in addition to any stack effect '**xt**' itself might have. Otherwise in '**tc**' the non-zero throw code is left, and the stack depth is restored. The values of the parameters for '**xt**' could have been modified. In general, there is nothing useful that can be done with those stack items. Since the stack depth is known, the application may **DROP** those items.

See also: '**THROW**' '**QUIT**' '**HANDLER**'

8.9.5 ERROR

Name: **ERROR**

Stackeffect: **n** —

Attributes:

Description: Notify the user that an uncaught exception or error with number '**n**' has occurred. The word that caused it is found using **WHERE** and displayed . Also '**n**' is passed to **MESSAGE** in order to give a description of the error, clamped to the range [-256, 63]. This word is executed by **THROW** before restarting the interpreter and can be revector to give more elaborate diagnostics.

See also: '**MESSAGE**' '**?ERROR**' '**WARNING**'

8.9.6 ERRSCR

Name: **ERRSCR**

Stackeffect: — **addr**

Attributes:

Description: A variable containing the address of the number of the screen from which messages are offset. Messages correspond with lines and the offset may be positive or negative. '**0 MESSAGE**' prints the first line of this screen. Traditionally this was screen 4, but the negative Unix error numbers makes this infeasible.

See also: '**C/L**' '**MESSAGE**'

8.9.7 MESSAGE

Name: **MESSAGE**

Stackeffect: **n** —

Attributes:

Description: **MESSAGE** is generally used to print error and warning messages. If **WARNING** is zero (disc unavailable), this is a noop. Print on the standard error channel the text of line '**n**' relative to screen **ERRSCR** . '**n**' may be positive or negative and beyond just screen **ERRSCR** . A certain range around 0 is reserved. The messages with small positive offset contain cforth error messages. The messages with small negative offset contain the strings belonging to the return values for Linux system calls . '**0 MESSAGE**' will print version information about the library file where the messages sit in.

See also: '**ERROR**' '**BLOCK-FILE**'

8.9.8 THROW

Name: **THROW**

Stackeffect: ... tc — ... / ... tc

Attributes: ISO

Description: If 'tc' is zero, it is merely discarded. If we are executing under control of a **CATCH**, see **CATCH** for the effect of a non-zero 'tc'. If we are executing not under control of a **CATCH**, a non-zero 'tc' gives a message to the effect that this exception has occurred and starts Forth anew.

See also: 'CATCH' 'QUIT' 'HANDLER' '?ERROR' 'ERROR'

8.9.9 WARNING

Name: **WARNING**

Stackeffect: — addr

Attributes: FIG,U

Description: A user variable containing a value controlling messages. If it is 1, a library file is assumed to be open, and messages are fetched from it. If it is 0, error messages will be presented by number only.

See also: 'MESSAGE' 'ERROR' 'ERRSCR'

8.9.10 WHERE

Name: **WHERE**

Stackeffect: — addr

Attributes: U

Description: A user variable pair which contains the start of the source and the position after the last character parsed when an error thrown by **?ERROR**, so not of exceptions thrown. The contents of **WHERE** is interpreted by **ERROR** if the corresponding exception was never caught.

See also: 'THROW' 'CATCH'

8.9.11 (ABORT")

Name: (ABORT")

Stackeffect: f —

Attributes:

Description: The run time action of **ABORT"**.

8.9.12 HANDLER

Name: **HANDLER**

Stackeffect: — addr

Attributes:

Description: A user variable address containing a pointer to the last exception intercepting frame activated by **CATCH**. It points into the return stack. If there is a **THROW**, the return stack is restored from **HANDLER** effecting a multiple level return. It is called a frame because more things are restored, such as the position of the data stack top, and the previous value of **HANDLER**.

See also: 'CATCH' 'THROW'

8.10 FILES

The wordset ‘FILES’ contains words to input and output to files, or load words from files. They are underlying the ‘BLOCKS’ facilities.

8.10.1 CLOSE-FILE

Name: CLOSE-FILE

Stackeffect: fileid — ior

Attributes: ISO

Description: Close the file with file handle in ‘fileid’. Return a result code into ‘ior’. The latter is the Linux error code negated, usable as a throw code.

See also: ‘OPEN-FILE’ ‘READ-FILE’ ‘WRITE-FILE’ ‘CREATE-FILE’ ‘DELETE-FILE’

8.10.2 CREATE-FILE

Name: CREATE-FILE

Stackeffect: sc u — fileid ior

Attributes: ISO

Description:

Create a file with name ‘sc’ and file access privileges ‘u’. If the file already exists, it is truncated to zero length. Return a file handle into ‘fileid’ and a result code into ‘ior’. The latter is the ‘errno’ negated, to be inspected using MESSAGE . The handle is open for READ_WRITE.

See also: ‘OPEN-FILE’ ‘READ-FILE’ ‘WRITE-FILE’ ‘DELETE-FILE’

8.10.3 DELETE-FILE

Name: DELETE-FILE

Stackeffect: sc — ior

Attributes: ISO

Description: Delete the file with name ‘sc’. Return a result code into ‘ior’. The latter is the ‘errno’ negated, to be inspected using MESSAGE .

See also: ‘OPEN-FILE’ ‘READ-FILE’ ‘WRITE-FILE’ ‘CREATE-FILE’

8.10.4 FILE-POSITION

Name: FILE-POSITION

Stackeffect: fd — ud ior

Attributes: ISO

Description:

‘ud’ is the file current position for the file that is open at ‘fd’. ‘ior’ is 0 for success, or otherwise ‘errno’ negated . Information about error codes can be found by MESSAGE .

See also: ‘OPEN-FILE’ ‘REPOSITION-FILE’

8.10.5 GET-FILE

Name: GET-FILE

Stackeffect: sc1 — sc2

Attributes:

Description: Get the content of the file with name ‘sc1’; leave it as a string ‘sc2’. Any errors are thrown. The file is permanently stored at HERE .

See also: ‘PUT-FILE’ ‘OPEN-FILE’ ‘THROW’

8.10.6 INCLUDED

Name: INCLUDED

Stackeffect: sc1 — i*x

Attributes: ISO

Description: Interpret the content of the file with name ‘sc1’ as if it was typed from the console, leaving result ‘i*x’. The file is permanently stored in the dictionary.

See also: ‘LOAD’

8.10.7 INCLUDE

Name: INCLUDE

Stackeffect: "name" — i*x

Attributes: ISO

Description: Interpret the content of the file with "name" as if it was typed from the console, leaving result ‘i*x’. The file is permanently stored in the dictionary, but trimmed in compiled programs.

See also: ‘LOAD’

8.10.8 OPEN-FILE

Name: OPEN-FILE

Stackeffect: sc fam — fileid ior

Attributes: ISO

Description: Open the file with name ‘sc’ and file access method ‘fam’. Return a file handle into ‘fileid’ and a result code into ‘ior’. The latter is the ‘errno’ error code negated, usable as a throw code. ‘fam’ is one of 0=READ_ONLY, 1=WRITE_ONLY, 2=READ_WRITE.

See also: ‘READ-FILE’ ‘WRITE-FILE’ ‘CREATE-FILE’ ‘DELETE-FILE’ ‘CLOSE-FILE’

8.10.9 PUT-FILE

Name: PUT-FILE

Stackeffect: sc1 sc2 —

Attributes:

Description: Save the *string constant* ‘sc1’ to a file with the name ‘sc2’. Any errors are thrown.

See also: ‘GET-FILE’ ‘OPEN-FILE’ ‘THROW’

8.10.10 READ-FILE

Name: READ-FILE

Stackeffect: addr n1 fd — n2 ior

Attributes: ISO

Description: Read ‘n’ characters to ‘addr’ from current position of the file that is open at ‘fd’. ‘n2’ is the number of characters successfully read, this may be zero. ‘ior’ is 0 for success, or otherwise ‘errno’ error code negated, usable as a throw code.

See also: ‘OPEN-FILE’ ‘WRITE-FILE’ ‘REPOSITION-FILE’ ‘BLOCK-READ’

8.10.11 REPOSITION-FILE

Name: REPOSITION-FILE

Stackeffect: ud fd — ior

Attributes: ISO

Description: Position the file that is open at 'fd' at position 'ud'. 'ior' is 0 for success, or otherwise 'errno' negated . Information about error codes can be found by MESSAGE .

See also: 'OPEN-FILE' 'READ-FILE' 'WRITE-FILE'

8.10.12 WRITE-FILE

Name: WRITE-FILE

Stackeffect: addr n fd — u1

Attributes: ISO

Description: Write 'n' characters from 'addr' to the file that is open at 'fd' , starting at its current position. 'u1' is 0 for success, or otherwise 'errno' error code negated, usable as a throw code.

See also: 'OPEN-FILE' 'READ-FILE' 'REPOSITION-FILE' 'BLOCK-WRITE'

8.10.13 RW-BUFFER

Name: RW-BUFFER

Stackeffect: — addr

Attributes:

Description: A constant that leaves the address of a disk buffer used by file i/o words.

See also: 'READ-FILE' 'OPEN-FILE' 'ZEN'

8.11 FORMATTING

The wordset 'FORMATTING' generates formatted output for numbers, i.e. printing the digits in a field with a certain width, possibly with sign etc. This is possible in any *number base* . (Normally base 10 is used, which means that digits are found as a remainder by dividing by 10). Formatting in Forth is always based on *double* numbers. Single numbers are handled by converting them to *double* first. This requires some double precision operators to be present in the Forth core. See Section 8.7 [DOUBLE], page 64, wordset. See Section 8.19 [MULTIPLYING], page 91, wordset.

8.11.1 #>

Name: #>

Stackeffect: d — sc

Attributes: ISO,FIG

Description: Terminates numeric output conversion by dropping 'd', leaving the formatted string 'sc' .

See also: '<#'

8.11.2 #S

Name: #S

Stackeffect: d1 — d2

Attributes: ISO,FIG

Description: Generates ASCII text in the text output buffer, by the use of # , until a zero double number 'd2' results. Used between <# and #> .

8.11.3

Name: #

Stackeffect: d1 — d2

Attributes: ISO,FIG

Description: Generate from a double number ‘d1’, the next ASCII character which is placed in an output string. Result ‘d2’ is the quotient after division by **BASE**, and is maintained for further processing. Used between <# and #> .

See also: ‘#S’

8.11.4 <#

Name: <#

No stackeffect

Attributes: ISO,FIG

Description: Setup for pictured numeric output formatting using the words: <# # #S

SIGN #> The conversion is done on a double number producing text growing down from PAD .

See also: ‘DPL’ ‘HLD’ ‘HOLD’ ‘FLD’

8.11.5 >NUMBER

Name: >NUMBER

Stackeffect: ud1 addr1 u1 — ud2 addr2 u2

Attributes: ISO

Description:

‘ud2’ is the result of converting the characters within the character string specified by ‘addr1 u1’ into digits, using the number in **BASE**, and adding each into ud1 after multiplying ‘ud1’ by the number in **BASE**. Conversion continues until a character that is not convertible is encountered or the string is entirely converted. ‘addr2’ is the location of the first unconverted character or the first character past the end of the string if the string was entirely converted. ‘u2’ is the number of unconverted characters in the string. If ‘ud2’ overflows, in ciforth ‘ud2’ will be incorrect, but no crash will result. Both - and + are considered unconvertible character’s by ‘>NUMBER’.

See also: ‘NUMBER’ ‘DIGIT’ ‘DPL’

8.11.6 BASE

Name: BASE

Stackeffect: — addr

Attributes: ISO,FIG,U

Description: A user variable containing the current number base used for input and output conversion.

See also: ‘DECIMAL’ ‘HEX’ ‘<#’

8.11.7 DECIMAL

Name: DECIMAL

No stackeffect

Attributes: ISO,FIG

Description: Set the numeric conversion **BASE** for decimal input-output.

See also: ‘HEX’

8.11.8 HEX

Name: **HEX**

No stackeffect

Attributes: ISO,FIG

Description: Set the numeric conversion **BASE** for hexadecimal (base 16) input-output.

See also: ‘**DECIMAL**’

8.11.9 HOLD

Name: **HOLD**

Stackeffect: **c** —

Attributes: ISO,FIG

Description: Add the character ‘**c**’ to the beginning of the output string. It must be executed for numeric formatting inside a **<#** and **#>** construct .

See also: ‘**#**’ ‘**DIGIT**’

8.11.10 SIGN

Name: **SIGN**

Stackeffect: **n** —

Attributes: ISO,FIG

Description: Add an ASCII minus-sign **-** inside a **<#** and **#>**

construct to the beginning of a converted numeric output string in the text output buffer when ‘**n**’ is negative. Must be used between **<#** and **#>** .

See also: ‘**HOLD**’

8.11.11 (NUMBER)

Name: **(NUMBER)**

Stackeffect: — **d1**

Attributes:

Description: Convert the ASCII text at the *current input source* with regard to **BASE** . The new value is accumulated into double number ‘**d1**’ , being left. A decimal point, anywhere, signifies that the input is to be considered as a double. ISO requires it to be at the end of the number. cforth allows any number of decimal points with the same meaning. cforth also allows any number of comma’s that are just ignored, to improve readability. If the first unconvertible digit is not a blank, this is an error.

See also: ‘**NUMBER**’ ‘**?BLANK**’

8.11.12 DIGIT

Name: **DIGIT**

Stackeffect: **c n1** — **n2 true (ok) c n1** — **x false (bad)**

Attributes:

Description: Converts the ASCII character ‘**c**’ (using base ‘**n1**’) to its binary equivalent ‘**n2**’ , accompanied by a true flag. If the conversion is invalid, leaves a don’t care value and a false flag.

8.11.13 DPL

Name: DPL

Stackeffect: — addr

Attributes: FIG,U

Description: A user variable containing the address of the decimal point on double integer input, or a *nil pointer*. During output it is free to use, e.g. to hold the output column location of a decimal point, in user generated formatting.

See also: ‘<#’ ‘FLD’ ‘HLD’

8.11.14 ECL

Name: ECL

Stackeffect: — addr

Attributes:

Description: A user variable containing the address of the exponential sign in a floating point input, or a *nil pointer*.

See also: ‘DPL’

8.11.15 FLD

Name: FLD

Stackeffect: — addr

Attributes: FIG,U

Description: A user variable for control of number output field width. Unused in the kernel of ciforth.

8.11.16 HLD

Name: HLD

Stackeffect: — addr

Attributes: FIG

Description: A user variable that holds the address of the latest character of text during numeric output conversion.

See also: ‘<#’ ‘DPL’ ‘FLD’

8.11.17 NUMBER

Name: NUMBER

Stackeffect: — s/d

Attributes:

Description:

This word is intended to be called from (aliased as) single character denotation words, marked as **PREFIX IMMEDIATE** . Therefore it decrements the parse pointer to include this first character. Starting with this character, it converts characters from the current input source into a number, and compiles or executes this number, depending on **STATE** . If the string contains a decimal point it is a double else a single integer number. If numeric conversion is not possible, an error message will be given. Any comma’s in the number are ignored, to help in structuring large numbers. Traditionally comma’s also signified double precision numbers. Revectoring **NUMBER** affects all applicable number prefixes. In this way floating point numbers can be accomodated.

See also: ‘BASE’ ‘(NUMBER)’

8.12 INITIALISATIONS

The wordset ‘INITIALISATIONS’ contains words to initialise, reinitialise or configure Forth.

8.12.1 +ORIGIN

Name: +ORIGIN

Stackeffect: n — addr

Attributes:

Description: Leave the memory address relative by ‘n’ bytes to the area from which the user variables are initialised, so one can access or modify the boot-up parameters. During run time user variables are fetched from the current user area, via a pointer at ‘0 +ORIGIN’. This can be swapped to get a fresh set of user variables, for multi-asking. One can access or modify the boot-up parameters, prior to saving a customised boot image. This will affect the initialisation by COLD.

See also: ‘USER’

8.12.2 ABORT

Name: ABORT

No stackeffect

Attributes: ISO,FIG

Description: Restart the interpreter. In addition and before the actions of QUIT, clear also the data stack and reset the exception mechanism. This word is silent. This may be confusing at times, because you can’t tell the difference between a word that is still busy or that has aborted.

See also: ‘WARM’ ‘INIT’

8.12.3 COLD

Name: COLD

No stackeffect

Attributes: FIG

Description: Initialise all user variables to their boot up values values, i.e. the stacks and the *dictionary pointer*. Initialise the system as per INIT. Handle command line options, if any. Show signon message and restart via ABORT. May be called from the terminal to remove application programs and restart, as long as there are no new vocabularies with definitions. But it is better to say BYE to Forth and start again.

See also: ‘WARM’ ‘INIT’ ‘OPTIONS’

8.12.4 DEV-MEM

Name: DEV-MEM

Stackeffect: — addr

Attributes:

Description: A variable containing the file descriptor where the device memory is accessible. If it contains a negative number, it indicates an error, probably a lack of privilege.

See also: ‘VMA-IO’ ‘PC!’

8.12.5 INIT

Name: INIT

No stackeffect

Attributes: FIG

Description: Initialise or reinitialise the system. Reset the data stack, the wordlists, the number base and the exception mechanism. Initialise the block mechanism. Any blocks that have not yet been written back to mass storage are discarded. Now open the file that contains the blocks, in read-only mode. After `INIT` we have the following situation. The search order contains the `FORTH` words, plus `ONLY` with i.a. number handling. Definitions are added to the `FORTH namespace`. The number base is decimal. .

See also: ‘`WARM`’ ‘`COLD`’ ‘`FORTH`’ ‘`BLOCK-INIT`’ ‘`BASE`’ ‘`SO`’

8.12.6 MMAP-IO

Name: `MMAP-IO`

No stackeffect

Attributes:

Description: Fills `VMA-IO` with the memory base address or else an error code. `DEV-MEM` has been filled at `COLD`. If that failed `VMA-IO` will contain a same negative number, that indicates the error.

See also: ‘`P!`’ ‘`VMA-IO`’

8.12.7 OK

Name: `OK`

No stackeffect

Attributes: `ISO,FIG`

Description: Takes care of printing the okay-message, after interpreting a line. Default it prints “OK” only for an interactive session in interpret `STATE`. It can be revector to show debugging info or give a prompt.

See also: ‘`QUIT`’ ‘`COLD`’

8.12.8 OPTIONS

Name: `OPTIONS`

Stackeffect: `ft — f2`

Attributes: `CI`

Description: Handle command line option. If an option is passed during startup execute the screen corresponding to the option letter and return a false flag into ‘`f2`’, otherwise leave a true flag. During startup this flag decides whether the signon message is displayed. An option can always decide to execute `.SIGNON`. By redefining `OPTIONS` as ‘`DROP 0`’

See also: ‘`COLD`’

8.12.9 PERIPHERALS

Name: `PERIPHERALS`

Stackeffect: `— addr`

Attributes:

Description: A variable containing the address offset of peripherals, like digital I/O pins and I2C interfaces reside in `DEV-MEM`

pseudo-file.

See also: ‘`P!`’ ‘`PC!`’

8.12.10 QUIT

Name: **QUIT**

No stackeffect

Attributes: ISO,FIG

Description: Restart the interpreter. Clear the return stack, stop compilation, and return control to the operators terminal, or to the redirected input stream. This means (**ACCEPT**) user input to somewhere in the terminal input buffer, and then **INTERPRET** with that as a **SOURCE** . No message is given.

See also: ‘**TIB**’ ‘**ABORT**’

8.12.11 VMA-IO

Name: **VMA-IO**

Stackeffect: — addr

Attributes:

Description: A variable containing the address where the memory mapped IO resides.

See also: ‘**P!**’ ‘**PC!**’

8.12.12 WARM

Name: **WARM**

No stackeffect

Attributes: FIG

Description: Perform a so called "warm" start. Reinitialise the system as per **INIT** . Show the signon message and restart via **ABORT** .

See also: ‘**ABORT**’

8.13 INPUT

The wordset ‘**INPUT**’ contains words to get input from the terminal and such. See Section 8.10 [FILES], page 69, for disk I/O. See Section 8.1 [BLOCKS], page 38, for access of blocks.

8.13.1 (ACCEPT)

Name: (**ACCEPT**)

Stackeffect: — sc

Attributes:

Description: Accept characters from the terminal, until a **RET** is received and return the result as a constant string ‘**sc**’. It doesn’t contain any line ending, but the buffer still does and after 1+ the string ends in a **LF**. The editing functions are the same as with **ACCEPT** . This is lighter on the system and sometimes easier to use than **ACCEPT**

This input remains valid until the next time that the console buffer is refilled.

See also: ‘**KEY**’ ‘**KEY?**’ ‘**ACCEPT**’ ‘**PP@@**’ ‘**REFILL-TIB**’

8.13.2 ACCEPT

Name: **ACCEPT**

Stackeffect: addr count — n

Attributes: ISO

Description: Transfer at most ‘**count**’ characters from the terminal to address, until a **RET** is received. The simple tty editing functions of Linux are observed, i.e. the “erase” (delete a

character) and “kill” (delete a line) characters. Typically these are the backspace key and ^U. Note that excess characters after ‘count’ are ignored. The number of characters not including the *RET* is returned into ‘n’.

See also: ‘(ACCEPT)’ ‘KEY’ ‘KEY?’ ‘(ACCEPT)’

8.13.3 KEY?

Name: KEY?

Stackeffect: — ff

Attributes: ISO

Description: Return into ‘ff’ whether a character is available. The next execution of KEY will return the character immediately.

See also: ‘KEY’ ‘ACCEPT’ ‘KEY?’

8.13.4 KEY

Name: KEY

Stackeffect: — c

Attributes: ISO,FIG

Description: Leave the ASCII value of the next terminal key struck.

See also: ‘ACCEPT’ ‘KEY?’

8.13.5 PP

Name: PP

Stackeffect: — addr

Attributes:

Description: A user variable containing a pointer within the current input text buffer (terminal or disc) from which the next text will be accepted. All parsing words use and move the value of PP. This is different from how ISO >IN works, in the sense that clearing it doesn’t reset the parse pointer to the start of the current line.

See also: ‘>IN’ ‘WORD’ ‘NAME’ ‘NUMBER’ ‘PARSE’ ‘PP@@’

8.13.6 RUBOUT

Name: RUBOUT

Stackeffect: — c

Attributes:

Description: A user variable, leaving the key code that must delete the last character from the input buffer. In this ciforth it is not used, as the terminal input editing is left to the host operating system.

See also: ‘USER’

8.13.7 TIB

Name: TIB

Stackeffect: — addr

Attributes: ISO,FIG,U

Description: A user variable containing the address of the terminal input buffer. Traditionally, this was used for file i/o too

See also: ‘QUIT’

8.13.8 (>IN)

Name: (>IN)

Stackeffect: — addr

Attributes:

Description: After forthsample(WANT -legacy-) this is used by the word `L_>IN` , to store the offset from the start within the current input text buffer (terminal or disc) from which the next text will be accepted, to get a behaviour more in accordance with the standard. All parsing words use and move the value of `>IN` .

See also: ‘>IN’ ‘PP’

8.13.9 REFILL-TIB

Name: REFILL-TIB

Stackeffect: —

Attributes:

Description: Accept characters from the terminal input stream such as to fill up TIB . Normally this means until a *RET*. It is now consumable by `ACCEPT` or after `SET-SRC` by Forth parsing words like `NAME` . The editing functions are those described by `ACCEPT` . Immediately, after `REFILL-TIB` ‘REMAINDER 2@’ defines the characters ready in the input buffer. All characters are retained including the *RET*.

If the input is redirected (such that characters after a *RET* are available) ‘REMAINDER 2@’ contains the part of TIB that is not yet consumed by (`ACCEPT`) , and outside the reach of `SRC` .

All system call errors result in an exception. For redirected I/O this word may generate an end-of-pipe exception.

See also: ‘ACCEPT’ ‘(ACCEPT)’

8.13.10 REMAINDER

Name: REMAINDER

Stackeffect: — addr

Attributes:

Description: A pointer to a constant string that contains the balance of characters fetched into the input buffer, but not yet consumed. Used as in ‘REMAINDER 2@’ .

See also: ‘REFILL-TIB’

8.13.11 SET-TERM

Name: SET-TERM

Stackeffect: len b —

Attributes:

Description: Set the terminal length to ‘len’ and toggle the `c_lflag` field with ‘b’ in the termio structure `TERMIO` . In particular toggling with `0x0A` makes that the terminal doesn’t wait for a *RET*. This word is invalid for pipes, and is replaced by a `2DROP` in that case.

See also: ‘SET-TERM’

8.13.12 TERMIO

Name: TERMIO

Stackeffect: — addr

Attributes:

Description: Leave the address of the terminal description, this has the layout of a c-structure `'termio'`.

See also: `'SET-TERM'`

8.14 JUGGLING

The wordset `'JUGGLING'` contains words that change order of data on the *data stack*. The necessity for this arise, because the data you want to feed to a Forth word is not directly accessible, i.e. on top of the stack. It is also possible that you need the same data twice, because you have to feed it to two different words. Design your word such that you need them as little as possible, because they are confusing.

8.14.1 2DROP

Name: 2DROP

Stackeffect: $n1\ n2\ \text{---}$

Attributes: ISO

Description: Drop the topmost two numbers (or one double number) from the stack.

See also: `'DROP'` `'2DUP'`

8.14.2 2DUP

Name: 2DUP

Stackeffect: $d\ \text{---}\ d\ d$

Attributes: ISO

Description: Duplicate the double number on the stack.

See also: `'OVER'`

8.14.3 2OVER

Name: 2OVER

Stackeffect: $d1\ d2\ \text{---}\ d1\ d2\ d1$

Attributes: ISO

Description: Copy the second stack double, placing it as the new top.

See also: `'OVER'`

8.14.4 2SWAP

Name: 2SWAP

Stackeffect: $d1\ d2\ \text{---}\ d2\ d1$

Attributes: ISO

Description: Exchange the top doubles on the stack.

See also: `'SWAP'`

8.14.5 ?DUP

Name: ?DUP

Stackeffect: $n1\ \text{---}\ n1$ (if zero) / $n1\ \text{---}\ n1\ n1$ (non-zero)

Attributes: ISO,FIG

Description: Reproduce `'n1'` only if it is non-zero. This is usually used to copy a value just before `IF`, to eliminate the need for an `ELSE` part to drop it.

See also: `'DUP'` `'_'`

8.14.6 DROP

Name: DROP

Stackeffect: n —

Attributes: ISO,FIG

Description: Drop the number from the stack.

See also: 'DUP' 'SWAP' 'OVER'

8.14.7 DUP

Name: DUP

Stackeffect: n — n n

Attributes: ISO,FIG

Description: Duplicate the value on the stack.

See also: 'OVER' 'SWAP' 'DROP'

8.14.8 NIP

Name: NIP

Stackeffect: $n1$ $n2$ — $n2$

Attributes: ISO

Description: Drop the second number from the stack.

See also: 'DUP' 'DROP' 'SWAP' 'OVER'

8.14.9 OVER

Name: OVER

Stackeffect: $n1$ $n2$ — $n1$ $n2$ $n1$

Attributes: ISO,FIG

Description: Copy the second stack value, placing it as the new top.

See also: 'DUP'

8.14.10 ROT

Name: ROT

Stackeffect: $n1$ $n2$ $n3$ — $n2$ $n3$ $n1$

Attributes: ISO,FIG

Description: Rotate the top three values on the stack, bringing the third to the top.

See also: 'SWAP'

8.14.11 SWAP

Name: SWAP

Stackeffect: $n1$ $n2$ — $n2$ $n1$

Attributes: ISO,FIG

Description: Exchange the top two values on the stack.

See also: 'ROT'

8.15 LIBRARY

The words described into library have nothing particular in common, except that they are available in the *LAB* and not the ciforth kernel. They are either words from the library that are sufficiently useful to merit being described here, or legacy words that were in the kernel in earlier versions. All of them can be loaded from the library by ‘WANT’ ‘LEGACY_WORD’.

8.15.1 L_>IN

Name: L_>IN

Stackeffect: — addr

Attributes: ISO,WANT

Description: Hides and replaces the user variable PP . All parsing words use and move the value of that user variable. Return a variable that contains the offset from the start within the current input text buffer (terminal or disc) from which the next text will be accepted. The legacy >IN is not actually a variable: its content must be fetched immediately, and changing it has no effect.

See also: ‘(>IN)’ ‘IN’

8.16 LOGIC

The wordset ‘LOGIC’ contains logic operators and comparison operators. A comparison operator (such as =) delivers a *Forth flag* , -1 for true, 0 for false, representing a condition (such as equality of two numbers). The number -1 has all bits set to one. The logical operators (AND etc.) work on all 64 bits, one by one. In this way they are useful for mask operations, as well as for combining conditions represented as flag’s. But beware that IF only cares whether the top of the stack is non-zero, such that – can mean non-equal to IF . Such conditions (often named just *flag* ’s) cannot be directly combined using logical operators, but ‘0= 0=’ can help.

8.16.1 0<

Name: 0<

Stackeffect: n — ff

Attributes: ISO,FIG

Description: Leave a true flag if the number is less than zero (negative), otherwise leave a false flag.

See also: ‘<’ ‘0=’

8.16.2 0=

Name: 0=

Stackeffect: n — ff

Attributes: ISO,FIG

Description: Leave a true flag ‘ff’ if the number ‘n’ is equal to zero, otherwise leave a false flag. It may be aliased to NOT , which inverts a flag.

See also: ‘=’ ‘0<’

8.16.3 <>

Name: <>

Stackeffect: n1 n2 — ff

Attributes: ISO

Description: Leave a true flag if ‘n1’ is not equal than ‘n2’ ; otherwise leave a false flag.

See also: ‘>’ ‘=’ ‘0<’

8.16.4 <

Name: <

Stackeffect: n1 n2 — ff

Attributes: ISO

Description: Leave a true flag if ‘n1’ is less than ‘n2’ ; otherwise leave a false flag.

See also: ‘=’ ‘>’ ‘0<’

8.16.5 =

Name: =

Stackeffect: n1 n2 — ff

Attributes: ISO,FIG

Description: Leave a true flag if ‘n1=n2’ ; otherwise leave a false flag.

See also: ‘<’ ‘>’ ‘0=’ ‘-’

8.16.6 >

Name: >

Stackeffect: n1 n2 — ff

Attributes: ISO

Description: Leave a true flag if ‘n1’ is greater than ‘n2’ ; otherwise leave a false flag.

See also: ‘<’ ‘=’ ‘0<’

8.16.7 AND

Name: AND

Stackeffect: n1 n2 — n3

Attributes: ISO,FIG

Description: Leave the bitwise logical and of ‘n1’ and ‘n2’ as ‘n3’ . For Forth flags (0 or -1) this is the *logical and* operator.

See also: ‘XOR’ ‘OR’

8.16.8 INVERT

Name: INVERT

Stackeffect: n1 — n2

Attributes: ISO

Description: Invert all bits of ‘n1’ leaving ‘n2’ . For pure flags (0 or -1) this is the *logical not* operator.

See also: ‘AND’ ‘OR’

8.16.9 OR

Name: OR

Stackeffect: n1 n2 — n3

Attributes: ISO,FIG

Description: Leave the bit-wise logical or of two 64-bit values. For Forth flags (0 or -1) this is the *logical or* operator.

See also: ‘AND’ ‘XOR’

8.16.10 U<

Name: U<

Stackeffect: u1 u2 — ff

Attributes: ISO

Description: Leave a true flag if ‘u1’ is less than ‘u2’ ; otherwise leave a false flag.(Interpreted as unsigned numbers).

See also: ‘<’

8.16.11 XOR

Name: XOR

Stackeffect: n1 n2 — n3

Attributes: ISO,FIG

Description: Leave the bitwise logical exclusive or of two 64-bit values. For Forth flags (0 or -1) this is the *logical xor* operator.

See also: ‘AND’ ‘OR’

8.17 MEMORY

The wordset ‘MEMORY’ contains words to fetch and store numbers from *double* s, *cell* s or bytes in memory. There are also words to copy blocks of memory or fill them, and words that fetch a *cell* , operate on it and store it back.

8.17.1 !

Name: !

Stackeffect: n addr —

Attributes: ISO,FIG

Description: Store all 64 bits of n at ‘addr’ .

See also: ‘@’ ‘C!’ ‘2!’ ‘PW!’ ‘PC!’

8.17.2 +!

Name: +!

Stackeffect: n addr —

Attributes: ISO,FIG

Description: Add ‘n’ to the value at ‘addr’.

See also: ‘TOGGLE’ ‘!’

8.17.3 2!

Name: 2!

Stackeffect: x1 x2 addr —

Attributes: ISO

Description: Store a pair of 64 bits values ‘x1’ ‘x2’ to consecutive cells at ‘addr’ . ‘x2’ is stored at the lowest address.

See also: ‘2@’ ‘!’ ‘C!’

8.17.4 2@

Name: 2@

Stackeffect: addr — x1 x2

Attributes: ISO

Description: Leave a pair of 64 bits values ‘x1’ ‘x2’ from consecutive cells at ‘addr’. ‘x2’ is fetched from the lowest address.

See also: ‘2!’ ‘@’ ‘C@’

8.17.5 @

Name: @

Stackeffect: addr — n

Attributes: ISO,FIG

Description: Leave the 64 bit contents ‘n’ of ‘addr’.

See also: ‘!’ ‘C@’ ‘2@’ ‘P@’ ‘PC@’ ‘FAR@’

8.17.6 ALIGNED

Name: ALIGNED

Stackeffect: addr1 — addr2

Attributes: ISO

Description: Make sure that ‘addr1’ is *aligned* by advancing it if necessary to ‘addr2’.

See also: ‘ALIGN’

8.17.7 ALIGN

Name: ALIGN

Stackeffect: —

Attributes: ISO

Description: Make sure that **HERE** is *aligned* by advancing it if necessary. This means that data of any size can be fetched from that address efficiently.

See also: ‘ALIGNED’

8.17.8 BIC

Name: BIC

Stackeffect: mask portaddr — n

Attributes: ISO,FIG

Description: ‘portaddr’ is the address of a 32-bit entity irrespective of cell-size. The bits present in ‘mask’ are cleared from ‘addr’ without affecting other bits.

See also: ‘BIS’ ‘!’ ‘@’ ‘PW@’ ‘PW!’

8.17.9 BIS

Name: BIS

Stackeffect: mask portaddr — n

Attributes: ISO,FIG

Description: ‘portaddr’ is the address of a 32-bit entity irrespective of cell-size. The bits present in ‘mask’ are set in ‘addr’ without affecting other bits.

See also: ‘BIC’ ‘!’ ‘@’ ‘PW@’ ‘PW!’

8.17.10 BLANK

Name: BLANK

Stackeffect: addr count —

Attributes: ISO

Description: This is shorthand for “BL FILL ”.

8.17.11 BM

Name: BM

Stackeffect: — addr

Attributes:

Description: A constant leaving the address of the lowest memory in use by Forth.

See also: ‘DP’ ‘EM’

8.17.12 C!

Name: C!

Stackeffect: b addr —

Attributes: ISO

Description: Store 8 bits of ‘b’ at ‘addr’ . In ciforth , running on the Intel architectures there are no restrictions regarding byte addressing.

See also: ‘C@’ ‘!’

8.17.13 C@

Name: C@

Stackeffect: addr — b

Attributes: ISO

Description: Leave the 8 bit contents of memory address. In ciforth , running on the Intel architectures there are no restrictions regarding byte addressing.

See also: ‘C!’ ‘@’ ‘2@’

8.17.14 CELL+

Name: CELL+

Stackeffect: n1 — n2

Attributes: ISO

Description: Advance the memory pointer ‘n1’ by one (in this case 64 bits) cell to ‘n2’. This is invaluable for writing portable code. Much of the library code of ciforth runs on both 16 and 32 bits systems, thanks to this.

8.17.15 CELLS

Name: CELLS

Stackeffect: n1 — n2

Attributes: ISO

Description: Return the equivalent of ‘n1’ cells in bytes: ‘n2’. This is invaluable for writing portable code. Much of the library code of ciforth runs on both 16 and 32 bits systems, thanks to this.

See also: ‘CELL+’

8.17.16 CHAR+

Name: **CHAR+**

Stackeffect: **n1 — n2**

Attributes: **ISO**

Description: Advance the memory pointer ‘**n1**’ by one character to ‘**n2**’. In cforth this means one byte. Bytes are the address units ISO is talking about. Unfortunately the ISO standard has no way to address bytes.

See also: ‘**CELL+**’

8.17.17 CHARS

Name: **CHARS**

Stackeffect: **n1 — n2**

Attributes: **ISO**

Description: Return the equivalent of ‘**n1**’ chars in bytes: ‘**n2**’. In cforth this is a NOOP. Unfortunately the ISO standard has no way to address bytes.

See also: ‘**CELLS**’

8.17.18 CMOVE

Name: **CMOVE**

Stackeffect: **from to count —**

Attributes:

Description: Move the ‘**count**’ quantity of characters beginning at address ‘**from**’ to address ‘**to**’. The contents of address **from** is moved first proceeding toward high memory, such that memory propagation occurs. As the Intel 86-family is byte-addressing there are no restrictions in cforth.

8.17.19 CORA

Name: **CORA**

Stackeffect: **addr1 addr2 len — n**

Attributes: **CIF**

Description: Compare the memory areas at ‘**addr1**’ and ‘**addr2**’ over a length ‘**len**’. For the first bytes that differ, return -1 if the byte from ‘**addr1**’ is less (unsigned) than the one from ‘**addr2**’, and 1 if it is greater. If all ‘**len**’ bytes are equal, return zero. This is an abbreviation of **COMPARE-AREA**. It would have been named ‘**COMPARE**’, if that were not taken by ISO.

8.17.20 EM

Name: **EM**

Stackeffect: **— addr**

Attributes:

Description: A constant leaving the address just above the highest memory in use by Forth.

See also: ‘**DP**’ ‘**BM**’

8.17.21 ERASE

Name: **ERASE**

Stackeffect: **addr n —**

Attributes: **ISO**

Description: This is shorthand for ‘**0 FILL**’.

See also: ‘**BLANK**’ ‘**FILL**’

8.17.22 FILL

Name: FILL

Stackeffect: addr u b —

Attributes: ISO,FIG

Description: If ‘u’ is not zero, store ‘b’ in each of ‘u’ consecutive bytes of memory beginning at ‘addr’ .

See also: ‘BLANK’ ‘ERASE’

8.17.23 L!

Name: L!

Stackeffect: n addr —

Attributes:

Description: Store the 32-bit contents of ‘n’ at ‘addr’ .

See also: ‘L@’ ‘!’ ‘C!’ ‘2!’ ‘PW!’ ‘PC!’

8.17.24 L@

Name: L@

Stackeffect: addr — n

Attributes: ISO,FIG

Description: Leave the 32 bit contents ‘n’ of ‘addr’ .

See also: ‘!’ ‘C@’ ‘2@’ ‘PW@’ ‘PC@’ ‘FAR@’

8.17.25 MOVE

Name: MOVE

Stackeffect: from to count —

Attributes:

Description: Move ‘count’ bytes beginning at address ‘from’ to address ‘to’, such that the destination area contains what the source area contained, regardless of overlaps. As the Intel 86-family is byte-addressing there are no restrictions.

8.17.26 P!

Name: P!

Stackeffect: n addr —

Attributes:

Description: Store all 64 bits of n at io-location ‘addr’ . Actually his is the same as !

See also: ‘@’ ‘C!’ ‘2!’ ‘PW!’ ‘PC!’

8.17.27 P@

Name: P@

Stackeffect: addr — n

Attributes:

Description: Leave the 64 bit contents ‘n’ of ‘addr’ which is an io mapped 64 bit peripheral.

See also: ‘!’ ‘C@’ ‘@’ ‘P!’ ‘PC@’

8.17.28 PC!

Name: PC!

Stackeffect: b port —

Attributes:

Description: Store a byte ‘b’ to the port address ‘port’. The ports are memory mapped. You can use ports only after asking permission (using e.g. ‘ioperm’) and being super user.

See also: ‘PC@’ ‘PW!’ ‘P@’ ‘!’

8.17.29 PC@

Name: PC@

Stackeffect: port — b

Attributes:

Description: Fetch a byte ‘b’ from the port address ‘port’. The ports are memory mapped. You can use ports only after asking permission (using e.g. ‘ioperm’) and being super user.

See also: ‘PC!’ ‘PW@’ ‘PW!’ ‘@’

8.17.30 PW!

Name: PW!

Stackeffect: n port —

Attributes:

Description: Store the 16-bit data ‘n’ to the 16-bits port address ‘port’. The ports are memory mapped. You can use ports only after asking permission (using e.g. ‘ioperm’) and being super user.

See also: ‘PW@’ ‘PC!’ ‘PC@’ ‘!’

8.17.31 PW@

Name: PW@

Stackeffect: port — n

Attributes:

Description: Fetch the 16-bit contents ‘n’ from the port address ‘port’. The ports are memory mapped. You can use ports only after asking permission (using e.g. ‘ioperm’) and being super user.

See also: ‘PW!’ ‘PC@’ ‘PC!’ ‘@’

8.17.32 TOGGLE

Name: TOGGLE

Stackeffect: addr b —

Attributes: NFIG

Description: Complement the contents of ‘addr’ by the bit pattern ‘b’ .

See also: ‘XOR’ ‘+!’

8.17.33 WITHIN

Name: WITHIN

Stackeffect: n1 n2 n3 — ff

Attributes: ISO

Description: Return a flag indicating that ‘n1’ is in the range ‘n2’ (inclusive) to ‘n3’ (non-inclusive). This works for signed as well as unsigned numbers. This is shorthand for: ‘OVER – >R – R U<’

See also: ‘<’ ‘U<’

8.18 MISC

The wordset ‘MISC’ contains words that defy categorisation.

8.18.1 .SIGNON

Name: .SIGNON

Stackeffect: —

Attributes:

Description: Print a message identifying the version of this Forth. The name of the processor known from the environment query CPU is printed using the bizarre convention of a base-36 number. This is a tribute to those FIG-pioneers.

See also: ‘ABORT’ ‘COLD’

8.18.2 EXECUTE

Name: EXECUTE

Stackeffect: xt —

Attributes: ISO,FIG

Description: Execute the definition whose *execution token* is given by ‘xt’ . The *code field address* serves as an execution token. (It even has offset 0, but one should not assume that a *DEA* is an execution token in portable code.)

See also: ‘,’ ‘>CFA’

8.18.3 NOOP

Name: NOOP

No stackeffect

Attributes:

Description: Do nothing. Primarily useful as a placeholder.

8.18.4 TASK

Name: TASK

No stackeffect

Attributes:

Description: A no-operation word which marks the boundary between the Forth system and applications.

See also: ‘COLD’

8.18.5 U0

Name: U0

Stackeffect: — addr

Attributes:

Description: A user variable, leaving the start address of the user area. This is for reference only. What is taken into account by user variables is the initialisation variable at ‘0 +ORIGIN’ . This might be used for task switching.

See also: ‘USER’ ‘+ORIGIN’

8.18.6 _

Name: _

Stackeffect: — x

Attributes:

Description: Leave an undefined value ‘x’. Presumably it is to be dropped at some time, or it is a place holder.

8.19 MULTIPLYING

The original 16 bits Forth’s have problems with overflow (see Section 8.21 [OPERATOR], page 94). Operators with intermediate results of double precision, mostly scaling operators, solve this and are present in the ‘MULTIPLYING’ wordset. In this 64 bit Forth you will have less need. Formatting is done with *double*’s exclusively, and relies on this wordset. Operators with mixed precision and unsigned operators allow to build arbitrary precision operators from them in *high level* code.

8.19.1 */MOD

Name: */MOD

Stackeffect: n1 n2 n3 — n4 n5

Attributes: ISO,FIG

Description: Leave the quotient ‘n5’ and remainder ‘n4’ of the operation ‘n1*n2/n3’ (using *symmetric division*). A double precision intermediate product is used giving correct results, unless ‘n4’ or ‘n5’ overflows. ‘n1 n2 * n3 /’ gives an incorrect answer as soon as ‘n1 n2 *’ overflows.

See also: ‘*/’ ‘/MOD’

8.19.2 */

Name: */

Stackeffect: n1 n2 n3 — n4

Attributes: ISO,FIG

Description: Leave the ratio ‘n4 = n1*n2/n3’ where all are signed numbers(using *symmetric division*). A double precision intermediate product is used giving correct results, unless ‘n4’ overflows.

See also: ‘*/MOD’ ‘/MOD’

8.19.3 FM/MOD

Name: FM/MOD

Stackeffect: d n1 — n2 n3

Attributes: ISO

Description: A mixed magnitude math operator which leaves the signed remainder ‘n2’ and signed quotient ‘n3’ from a double number dividend ‘d’ and divisor ‘n1’. This is floored division, i.e. the remainder takes its sign from the divisor.

See also: ‘SM/REM’ ‘UDM/MOD’ ‘/’ ‘M*’

8.19.4 M*

Name: M*

Stackeffect: n1 n2 — d

Attributes: ISO,FIG

Description: A mixed magnitude math operation which leaves the double number ‘d’ : the signed product of two signed numbers ‘n1’ and ‘n2’ .

See also: ‘UDM/MOD’ ‘SM/REM’ ‘*’

8.19.5 SM/REM

Name: SM/REM

Stackeffect: d n1 — n2 n3

Attributes: ISO

Description: A mixed magnitude math operator which leaves the signed remainder ‘n2’ and signed quotient ‘n3’ from a double number dividend ‘d’ and divisor ‘n1’. This is a symmetric division, i.e. the remainder takes its sign from the dividend.

See also: ‘UDM/MOD’ ‘/’ ‘M*’

8.19.6 UDM/MOD

Name: UDM/MOD

Stackeffect: ud1 u2 — u3 ud4

Attributes: CIF,FIG

Description: An unsigned mixed magnitude math operation which leaves a double quotient ‘ud4’ and remainder ‘u3’ , from a double dividend ‘ud1’ and single divisor ‘u2’.

See also: ‘UM/MOD’ ‘SM/REM’ ‘M*’

8.19.7 UM*

Name: UM*

Stackeffect: u1 u2 — ud

Attributes: ISO

Description: A mixed magnitude math operation which leaves the double number ‘ud’ : the unsigned product of two unsigned numbers ‘u1’ and ‘u2’ .

See also: ‘UM/MOD’ ‘M*’ ‘*’

8.19.8 UM/MOD

Name: UM/MOD

Stackeffect: ud u1 — u2 u3

Attributes: ISO

Description: Leave the unsigned remainder ‘u2’ and unsigned quotient ‘u3’ from the unsigned double dividend ‘ud’ and unsigned divisor ‘u1’ .

See also: ‘UM*’ ‘SM/REM’ ‘/’

8.20 OPERATINGSYSTEM

The wordset ‘OPERATINGSYSTEM’ contains words that call the underlying operating system or functions available in the BIOS-rom.

8.20.1 ARGS

Name: ARGS

Stackeffect: — addr

Attributes:

Description: Return the **addr** of **ARGS** a user variable that contains a system dependant pointer to any arguments that are passed from the operating system to **ciforth** during startup.

In this **ciforth** it points to an area with the argument count, followed by a null ended array of arguments strings, then by a null ended array of environment strings.

See also: 'SYSTEM'

8.20.2 BYE

Name: **BYE**

Stackeffect: —

Attributes: ISO

Description: Return to the host environment Linux.

See also: 'COLD' 'EXIT-CODE'

8.20.3 EXIT-CODE

Name: **EXIT-CODE**

Stackeffect: **addr** —

Attributes:

Description: Return '**addr**' the address of a variable with the exit code. Its content is passed to the host environment while going **BYE** . It is custom to return zero if there are no errors. Linux allows only single byte return codes.

See also: 'BYE'

8.20.4 MS

Name: **MS**

Stackeffect: **n** —

Attributes: ISO

Description: Wait for '**n**' milliseconds.

See also: 'KEY?'

8.20.5 SHELL

Name: **SHELL**

Stackeffect: —**addr**

Attributes:

Description: Leave the address '**addr**' of a counted string, the name of a file that contains the command interpreter, or shell. This name may be changed and is used by the **SYSTEM** command. The name may contain a path and be at most 252 characters long. The default name is **/bin/sh** .

See also: 'SYSTEM'

8.20.6 SYSTEM

Name: **SYSTEM**

Stackeffect: **sc** —

Attributes: ISO

Description: Have the operating system execute the command contained in the string '**sc**'.

See also: 'BLOCK' '?ERROR' '?ERRUR'

8.20.7 XOS5

Name: XOS5

Stackeffect: n1 n2 n3 n4 n5 n—ret

Attributes:

Description: Do a traditional Unix type system call ‘n’ (man 2) with parameters ‘n1 n2 n3 n4 n5’. ‘ret’ is the return value of the call. If it is negative, it is mostly an error, such as known by **errno** . This makes available **all** facilities present in Linux.

See also: ‘?ERRUR’

8.20.8 XOS7

Name: XOS7

Stackeffect: n1 n2 n3 n4 n5 n6 n7 n—ret

Attributes:

Description: Do a traditional Unix type system call ‘n’ (man 2) with parameters ‘n1 n2 n3 n4 n5 n6 n7’. ‘ret’ is the return value of the call. If it is negative, it is mostly an error, such as known by **errno** . This makes available **all** facilities present in Linux.

See also: ‘?ERRUR’

8.20.9 XOS

Name: XOS

Stackeffect: n1 n2 n3 n—ret

Attributes:

Description: Do a traditional Unix type system call ‘n’ (man 2) with parameters ‘n1 n2 n3’. ‘ret’ is the return value of the call. If it is negative, it is mostly an error, such as known by **errno** . This makes available all facilities present in Linux, except those with 4 or 5 parameters that are handled by XOS5 .

See also: ‘?ERRUR’

8.20.10 ZEN

Name: ZEN

Stackeffect: sc — addr

Attributes:

Description: Leaves an address that contains a zero-ended (c-type) equivalent of ‘sc’. The same buffer is reused, such that this word is not reentrant. Use the word immediately, e.g. its intended used is passing parameters to the operating system. In fact this is **RW-BUFFER** .

See also: ‘OPEN-FILE’ ‘XOS’ ‘XOS5’

8.21 OPERATOR

The wordset ‘OPERATOR’ contains the familiar operators for addition, multiplication etc. The result of the operation is always an integer number, so division can’t be precise. On ciforth all division operations are compatible with *symmetric division* .

The ISO standard require a Forth to choose between floored or symmetric division for its standard operations. Divisions involving negative numbers have an interpretation problem. In any case we want the combination of / and MOD (remainder) to be such that you can get the original ‘n’ back from the two values left by ‘n m MOD’ and ‘n m /’ by performing ‘m * +’ . This is true for all Forth’s. On ciforth the / is a *symmetric division* , i.e. ‘-n m /’ give the same result as ‘n m /’ , but negated. The foregoing rule now has the consequence that ‘m MOD’ has ‘2|m|-1’

possible outcomes instead of ' $|m|$ '. This is very worrisome for mathematicians, who stick to the rule that ' $m \text{ MOD}$ ' has ' $|m|$ ' outcomes: ' $0 \dots |m|-1$ ', or ' $-|m|+1 \dots 0$ ' for negative numbers. (*floored division*).

8.21.1 *

Name: *

Stackeffect: $n1 \ n2 \rightarrow n3$

Attributes: ISO,FIG

Description: Leave the signed product ' $n3$ ' of two signed numbers ' $n1$ ' and ' $n2$ '.

See also: '+', '-', '/', 'MOD'

8.21.2 +

Name: +

Stackeffect: $n1 \ n2 \rightarrow \text{sum}$

Attributes: ISO,FIG

Description: Leave the sum of ' $n1$ ' and ' $n2$ '.

See also: '-', '*', '/', 'MOD'

8.21.3 -

Name: -

Stackeffect: $n1 \ n2 \rightarrow \text{diff}$

Attributes: ISO,FIG

Description: Leave the difference of ' $n1$ ' and ' $n2$ '.

See also: 'NEGATE', '+', '*', '/', 'MOD'

8.21.4 /MOD

Name: /MOD

Stackeffect: $n1 \ n2 \rightarrow \text{rem quot}$

Attributes: ISO,FIG

Description: Leave the remainder and signed quotient of ' $n1$ ' and ' $n2$ '. The remainder has the sign of the dividend (i.e. *symmetric division*).

See also: '*/MOD', '*/' 'SM/REM'

8.21.5 /

Name: /

Stackeffect: $n1 \ n2 \rightarrow \text{quot}$

Attributes: ISO,FIG

Description: Leave the signed quotient of ' $n1$ ' and ' $n2$ '. (using *symmetric division*).

See also: '+', '-', '*', 'MOD', '*/MOD'

8.21.6 ABS

Name: ABS

Stackeffect: $n \rightarrow u$

Attributes: ISO,FIG

Description: Leave the absolute value of ' n ' as ' u '.

See also: 'DABS'

8.21.7 ARSHIFT

Name: ARSHIFT

Stackeffect: $n1\ n \rightarrow n2$

Attributes: ISO

Description: Perform a **arithmetic shift** of the bits of ‘ $n1$ ’ to the right by ‘ n ’ places. Put the highest bit into the places uncovered by the shift.

See also: ‘LSHIFT’ ‘2/’

8.21.8 LSHIFT

Name: LSHIFT

Stackeffect: $u1\ n \rightarrow u2$

Attributes: ISO

Description: Perform a **logical shift** of the bits of ‘ $u1$ ’ to the left by ‘ n ’ places. Put zero into the places uncovered by the shift.

See also: ‘RSHIFT’ ‘2*’

8.21.9 MAX

Name: MAX

Stackeffect: $n1\ n2 \rightarrow \max$

Attributes: ISO,FIG

Description: Leave the greater of two numbers.

See also: ‘MIN’

8.21.10 MIN

Name: MIN

Stackeffect: $n1\ n2 \rightarrow \min$

Attributes: ISO,FIG

Description: Leave the smaller of two numbers.

See also: ‘MAX’

8.21.11 MOD

Name: MOD

Stackeffect: $n1\ n2 \rightarrow \text{mod}$

Attributes: ISO,FIG

Description: Leave the remainder of ‘ $n1$ ’ divided by ‘ $n2$ ’, with the same sign as ‘ $n1$ ’ (i.e. *symmetric division*).

See also: ‘+’ ‘-’ ‘*’ ‘/’ ‘MOD’ ‘*/MOD’

8.21.12 NEGATE

Name: NEGATE

Stackeffect: $n1 \rightarrow n2$

Attributes: ISO,FIG

Description: Leave the two’s complement of a number, i.e. ‘ $n2$ ’ is ‘ $-n1$ ’

See also: ‘-’

8.21.13 RSHIFT

Name: RSHIFT

Stackeffect: u1 n — u2

Attributes: ISO

Description: Perform a **logical shift** of the bits of ‘u1’ to the right by ‘n’ places. Put zero into the places uncovered by the shift.

See also: ‘LSHIFT’ ‘2/’

8.22 OUTPUT

The wordset ‘OUTPUT’ contains words to output to the terminal and such. See Section 8.10 [FILES], page 69, for disk I/O. See Section 8.1 [BLOCKS], page 38, for blocks.

8.22.1 (D.R)

Name: (D.R)

Stackeffect: d n —sc

Attributes: ISO,FIG

Description: Format a signed double number ‘d’ right aligned in a field ‘n’ characters wide to the string ‘sc’. Enlarge the field, if needed. So a field length of 0 results effectively in free format.

See also: ‘OUT’ ‘D.’ ‘D.R’

8.22.2 ."

Name: ."

No stackeffect

Attributes: ISO,FIG,I

Description: Used in the form: ‘.” cccc”’ In a definition it compiles an in-line string ‘cccc’ (as if the denotation "cccc" was used) followed by TYPE . In ciforth .” behaves the same way in interpret mode. In ciforth the number of characters has no limit. In ciforth .” always has an effect on HERE during interpretation. In ISO programs you may only use this word during compilation. We recommend that ‘.” cccc”’ is replaced by “cccc" TYPE’.)

See also: ‘OUT’

8.22.3 .(

Name: .(

No stackeffect

Attributes: I

Description: In ciforth this is an alias for .” , except that the string is closed with) instead of parsed as per " . In ISO programs you may only use this word while interpreting. We recommend that ‘.(cccc)’ is replaced by “cccc" TYPE’.

See also: ‘OUT’ ‘.’ ‘D.R’

8.22.4 .R

Name: .R

Stackeffect: n1 n2 —

Attributes:

Description: Print a signed number ‘n1’ right aligned in a field ‘n2’ characters wide. Enlarge the field, if needed. So a field length of 0 results effectively in free format.

See also: ‘OUT’ ‘.’ ‘(D.R)’

8.22.5 .

Name: .

Stackeffect: n —

Attributes: ISO,FIG

Description: Print the number ‘n1’ observing the current **BASE** , followed by a blank.

See also: ‘OUT’ ‘U.’ ‘.R’ ‘D.R’ ‘D.’ ‘(D.R)’

8.22.6 ?

Name: ?

Stackeffect: addr —

Attributes: ISO,FIG

Description: Print the value contained at the address ‘addr’ observing the current **BASE** , followed by a blank.

See also: ‘OUT’ ‘.’

8.22.7 CR

Name: CR

No stackeffect

Attributes: ISO,FIG

Description: Transmit character(s) to the terminal, that result in a "carriage return" and a "line feed". This means that the cursor is positioned at the start of the next line, if needed the display is scrolled.

See also: ‘OUT’

8.22.8 D.R

Name: D.R

Stackeffect: d n —

Attributes: ISO,FIG

Description: Print a signed double number ‘d’ right aligned in a field ‘n’ characters wide. Enlarge the field, if needed. So a field length of 0 results effectively in free format.

See also: ‘OUT’ ‘D.’ ‘(D.R)’

8.22.9 D.

Name: D.

Stackeffect: d —

Attributes: ISO,FIG

Description: Print the signed double number ‘d’, observing the current **BASE** , followed by a blank.

See also: ‘OUT’ ‘.’ ‘D.R’ ‘(D.R)’

8.22.10 EMIT

Name: EMIT

Stackeffect: c —

Attributes: ISO,FIG

Description: Transmit ASCII character ‘c’ to the output device. For this ciforth all terminal I/O goes through **TYPE** . In this ciforth **EMIT** maintains **OUT** .

See also: ‘TYPE’ ‘OUT’

8.22.11 ETYPE

Name: ETYPE

Stackeffect: addr count —

Attributes:

Description: Transmit ‘count’ characters from ‘addr’ to the standard error device. It is high level so error output can be redirected, by *revectoring* it. Or you may use redirection by Linux. In this ciforth strings may contain embedded *LF* ’s with the effect of a new line at that point in the output.

See also: ‘EMIT’ ‘TYPE’

8.22.12 OUT

Name: OUT

Stackeffect: — addr

Attributes: U

Description: A user variable that reflects the position at the current line of the output device where the next character transmitted will appear. The first position is zero. Only an explicit *CR* will reset *OUT* , not an *LF* embedded in a string that is *TYPE* d.

See also: ‘EMIT’ ‘TYPE’ ‘CR’

8.22.13 SPACES

Name: SPACES

Stackeffect: n —

Attributes: ISO,FIG

Description: If ‘n’ is greater or equal to zero, display as much spaces.

See also: ‘SPACE’ ‘OUT’

8.22.14 SPACE

Name: SPACE

No stackeffect

Attributes: ISO,FIG

Description: Transmit an ASCII blank to the output device.

See also: ‘EMIT’ ‘OUT’

8.22.15 TYPE

Name: TYPE

Stackeffect: addr count —

Attributes: ISO,FIG

Description: Transmit ‘count’ characters from ‘addr’ to the output device. All terminal I/O goes through this word. It is high level so terminal I/O can be redirected, by *revectoring* it and the usual redirection or ‘tee’-ing by Linux. In this ciforth strings may contain embedded *LF* ’s with the effect of a new line at that point in the output, however in that case *OUT* is not observed.

See also: ‘EMIT’ ‘OUT’ ‘ETYPE’

8.22.16 U.

Name: U.

Stackeffect: u —

Attributes: ISO

Description: Print the unsigned number ‘u’ observing the current **BASE** , followed by a blank.

See also: ‘OUT’ ‘.’ ‘.R’ ‘D.R’ ‘D.’ ‘(D.R)’

8.23 PARSING

The *outer interpreter* is responsible for parsing, i.e. it gets a word from the *current input source* and interprets or compiles it, advancing the IN pointer. The wordset ‘PARSING’ contains the words used by this interpreter and other words that consume characters from the input source. In this way the outer interpreter need not be very smart, because its capabilities can be extended by new words based on those building blocks.

8.23.1 ?BLANK

Name: ?BLANK

Stackeffect: c — ff

Attributes:

Description: For the character ‘c’ return whether this is considered to be white space into the flag ‘ff’ . At least the space, ASCII null, the tab and the carriage return and line feed characters are white space.

See also: ‘BL’ ‘SPACE’

8.23.2 CHAR

Name: CHAR

Stackeffect: — c

Attributes: ISO,I

Description: Parse a word and leave ‘c’ the first non blank char of that word in the input source. If compiled the searching is done while the word being compiled is executed. Because this is so confusing, it is recommended that one never compiles or postpones CHAR .

See also: ‘Prefix_&’ ‘[CHAR]’ ‘’’

8.23.3 EVALUATE

Name: EVALUATE

Stackeffect: sc — ??

Attributes: ISO

Description: Interpret the content of ‘sc’. Afterwards return to the *current input source* .

See also: ‘LOAD’ ‘INCLUDE’ ‘SET-SRC’

8.23.4 INTERPRET

Name: INTERPRET

Stackeffect: ?? — ??

Attributes:

Description: Repeatedly fetch the next text word from the *current input source* and execute it (STATE is not 1) or compile it (STATE is 1). A word is blank-delimited and looked up in the vocabularies of *search-order* . It can be either matched exactly, or it can match a prefix. A

word that matches a prefix is called a *denotation* ; mostly this is a number. Prefixes are present in **ONLY** which is the last wordlist in the search order, and the minimum search order. If it is not found at all, it is an **ERROR** . A *denotation* is a number, a double number, a character or a string etc. Denotations are handled respectively by the words **0 ... F & "** and any other word of the **ONLY** wordlist, depending on the first character or characters.

A number is converted according to the current base. If a decimal point is found as part of a number, the number value that is left is a double number, otherwise it is a single number. Comma's are ignored in ciforth.)

See also: 'WORD' 'NUMBER' 'BLK' 'DPL'

8.23.5 NAME

Name: NAME

Stackeffect: — sc

Attributes: CI

Description: Parse the *current input source* for a word, i.e. blank-delimited as per ?BLANK . Skip leading delimiters then advance the input pointer to past the next delimiter or past the end of the input source. Leave the word found as a string constant 'sc'. As it goes with string constants, you may not alter its content, nor assume anything is appended. Note that this is more deserving of the name "WORD" than what is in the ISO standard, that can be used to parse lines.

See also: 'BLK' 'WORD' 'IN'

8.23.6 PARSE

Name: PARSE

Stackeffect: c — sc

Attributes:

Description: Scan the *current input source* for the character 'c' . Return 'sc': a string from the current position in the input stream, ending before the first such character, or at the end of the current input source if it isn't there. The character is consumed. As it goes with *string constants*, you may not alter its content, nor assume anything is appended. So no leading delimiters are skipped.

See also: 'WORD' 'NAME'

8.23.7 PP@@

Name: PP@@

Stackeffect: —addr c

Attributes: CI

Description: Parse the *current input source* leaving the next character 'c' and its address 'addr' . If at the end of the input source, leave a pointer past the end and a zero. Advance the input pointer to the next character.

See also: 'BLK' 'WORD' 'PP'

8.23.8 RESTORE-INPUT

Name: RESTORE-INPUT

Stackeffect: n1 n2 n3 3—f

Attributes: ISO,WANT

Description: Restore the input source stream from what was saved by SAVE-INPUT . ciforth is always able to restore the input across different input sources, as long as the input to be restored

was not exhausted. This has the effect of chaining, and doesn't affect the return from nested calls be it interpreting, loading or evaluating. ciforth always returns a true into 'f'. The input source abandoned will never be closed properly, so use should be restricted to the same input source.

See also: 'SAVE' 'SAVE-INPUT'

8.23.9 RESTORE

Name: RESTORE

Stackeffect: —

Attributes:

Description: This must follow a **SAVE** in the same definition. Restore the content of **SRC** from the return stack thus restoring the *current input source* to what it was when the **SAVE** was executed.

See also: 'SET-SRC' 'RESTORE-INPUT'

8.23.10 SAVE-INPUT

Name: SAVE-INPUT

Stackeffect: — n1 n2 n3 3

Attributes: ISO,WANT

Description: Get a complete specification of the input source stream. For ciforth this is the content of **SRC** . ciforth needs 3 cells, and is always able to **RESTORE** an input saved like this. In practice the use of **SAVE-INPUT** should be restricted to restoring input of the same stream.

See also: 'SAVE' 'RESTORE-INPUT'

8.23.11 SAVE

Name: SAVE

Stackeffect: —

Attributes:

Description: Save the content of **SRC** on the return stack to prepare for changing the *current input source* . This must be balanced by a **RESTORE** in the same definition. **CO** can be used between the two.

See also: 'SET-SRC' 'SAVE-INPUT'

8.23.12 SET-SRC

Name: SET-SRC

Stackeffect: sc —

Attributes:

Description: Make the *string constant* 'sc' the *current input source* . This input is chained, i.e. exhausting it has the same effect as exhausting the input that called **SET-SRC** . In practice this word is almost always preceeded by a call to **SAVE** and followed by a call to **INTERPRET** .

See also: 'SRC' 'EVALUATE' 'INTERPRET'

8.23.13 SOURCE

Name: SOURCE

Stackeffect: — addr n1

Attributes: ISO

Description: Return the address and length of the *current input source* .

See also: 'SRC'

8.23.14 SRC

Name: SRC

Stackeffect: addr —

Attributes:

Description: Return the address ‘**addr**’ of the *current input source* specification, allocated in the user area. It consists of three cells: the lowest address of the parse area, and the non-inclusive highest address of the parse area and a pointer to the next character to be parsed. Changing ‘SRC’ takes immediate effect, and must be atomic, by changing only the third cell or by e.g. using SET-SRC . The third cell has the alias ‘IN’ . Words like ‘>IN BLK SOURCE’ are secondary, and return their output by “second-guessing” ‘SRC’ .

See also: ‘SAVE’ ‘RESTORE’ ‘BLK’

8.23.15 STATE

Name: STATE

Stackeffect: — addr

Attributes: ISO,U

Description: A user variable containing the compilation state. A non-zero value indicates compilation.

8.23.16 WORD

Name: WORD

Stackeffect: c —addr

Attributes: ISO,FIG,WANT

Description: Parse the ‘**current input source**’ using ‘c’ for a delimiter. Skip leading delimiters then advance the input pointer to past the next delimiter or past the end of the input source. Leave at ‘**addr**’ a copy of the string, that was surrounded by ‘c’ in the input source. This is an oldfashioned string to be fetched by COUNT , not \$@ . In ciforth the character string is positioned at the dictionary buffer HERE . WORD leaves the character count in the first byte, the characters, and ends with two or more blanks.

See also: ‘NAME’ ‘PARSE’ ‘BLK ’ ‘IN’

8.23.17 [CHAR]

Name: [CHAR]

Stackeffect: — c

Attributes: ISO I

Description: A compiling word. Parse a word. Add the run time behaviour: leave ‘c’, the first non blank char of that word in the input source. In ciforth this word works also in interpret mode.

See also: ‘Prefix_&’ ‘CHAR’

8.23.18 [

Name: [

No stackeffect

Attributes: ISO,FIG,I,

Description: Used in a colon-definition in form:

```
: xxx      [ words ]    more  ;
```

Suspend compilation. The words after [are executed, not compiled. This allows calculation or compilation exceptions before resuming compilation with]

See also: ‘LITERAL ’ ‘]’

8.23.19 \

Name: \

No stackeffect

Attributes: ISO,I

Description: Used in the form: ‘\ cccc’ Ignore a comment that will be delimited by the end of the current line. May occur during execution or in a colon-definition. Blank space after the word \ is required.

See also: ‘(’

8.23.20]

Name:]

No stackeffect

Attributes: ISO,FIG

Description: Resume compilation, to the completion of a colon-definition.

See also: ‘[’

8.23.21 (

Name: (

No stackeffect

Attributes: ISO,FIG,I

Description: Used in the form: ‘(cccc’). Ignore a comment that will be delimited by a right parenthesis that must be in the same input source, i.e. on the same line for terminal input, or in the same string, block or file, when that is the input. It is an immediate word. So colon definitions can be commented too. A blank after the word ‘(’ is required.

See also: ‘\’

8.24 SCREEN

Most of the *blocks* mass storage is used for *screen* ’s that have 16 lines of 64 characters. They are used for source code and documentation. Each screen is one **BLOCK** as required by ISO. The ‘**SCREEN**’ wordset contains facilities to view screens, and *load* them, that is compiling them and thus extending the base system. A system is customized by loading source screens, possibly one of these extension is a text editor for screens.

8.24.1 (LINE)

Name: (LINE)

Stackeffect: n1 n2 — sc

Attributes:

Description: Convert the line number ‘n1’ and the screen ‘n2’ to a string ‘sc’ the content of the line (without the trailing new line).

See also: ‘LINE’

8.24.2 C/L

Name: C/L

Stackeffect: — c

Attributes:

Description: A constant that leaves the number of characters on a line of a standard screen: 64. The last character of each line is a *LF*.

See also: 'LIST' 'LINE'

8.24.3 INDEX

Name: INDEX

Stackeffect: from to —

Attributes:

Description: Print the first line of each screen over the inclusive range 'from' , 'to' . This is used to view the comment lines of an area of text on disc screens.

See also: 'LIST'

8.24.4 LIST

Name: LIST

Stackeffect: n —

Attributes: ISO,FIG

Description: Display the ASCII text of screen 'n'. The number of the screen is always printed in decimal. SCR contains the screen number during and after this process.

See also: 'BLOCK'

8.24.5 LOAD

Name: LOAD

Stackeffect: n — ??

Attributes: ISO,FIG

Description: Interrupt the *current input source* in order to interpret screen 'n' . The stack changes in according with the words executed. At the end of the screen, barring errors or forced changes, it continues with the interrupted input source.

See also: 'BLOCK' '#BUFF' 'THRU' 'QUIT' 'EXIT' '-->' 'LIST'

8.24.6 LOCK

Name: LOCK

Stackeffect: n —

Attributes: CI

Description: Lock the block 'n'. Multiple locks are possible, and require multiple unlocks. Probably, because it is to become the *current input source* . The result is that its buffer will not be reclaimed until an UNLOCK occurs.

See also: 'BLOCK' 'UNLOCK' '#BUFF'

8.24.7 R#

Name: R#

Stackeffect: — addr

Attributes: U

Description: A user variable which may contain the location of an editing cursor, or other file related function. Unused in the kernel of ciforth.

8.24.8 SCR

Name: SCR

Stackeffect: — addr

Attributes: U

Description: A user variable containing the screen number most recently reference by LIST .

See also: 'BLOCK'

8.24.9 THRU

Name: THRU

Stackeffect: n1 n2 — ??

Attributes: ISO,FIG

Description: Interrupt the *current input source* in order to interpret screen 'n1' through 'n2' (inclusive). The stack changes in according with the words executed. At the end of the screens, barring errors or forced changes, it continues with the interrupted input source.

See also: '#BUFF' 'BLOCK' 'LOAD' 'QUIT' 'EXIT' '-->'

8.24.10 TRIAD

Name: TRIAD

Stackeffect: scr —

Attributes:

Description: Display on the selected output device the three screens which include that numbered 'scr' , beginning with a screen evenly divisible by three. Output is suitable for source text records, and includes a reference line at the bottom taken from line 0 of the first error screen.

See also: 'MESSAGE' 'ERRSCR '

8.24.11 UNLOCK

Name: UNLOCK

Stackeffect: n —

Attributes: CI

Description: Unlock the block 'n'. Probably, because it is no longer the *current input source* . The result is that its buffer can again be reclaimed. Unlocking without a previous lock may lead to a crash.

See also: 'LOCK' '#BUFF'

8.24.12 (BLK)

Name: (BLK)

Stackeffect: — addr

Attributes: U

Description: When the standard word BLK is used, this user variable reflects the state of the *current input source* . It indicates the block number being interpreted, or zero, if input is being taken from the terminal input buffer. Changing BLK has no effect, and its content must be fetched before the *current input source* has changed.

See also: 'BLOCK' 'TIB'

8.24.13 BLK

Name: BLK

Stackeffect: — addr

Attributes: ISO

Description: When the standard word ‘BLK’ is used, the content of the user variable ‘(BLK)’ is refreshed to reflect the state of the current input source and its address is returned in ‘**addr**’. It indicates the block number being interpreted, or zero, if input is being taken from the terminal input buffer. In *ciforth* changing the content at ‘**addr**’ has no effect, and its content must be fetched before the *current input source* has changed.

See also: ‘BLOCK’ ‘TIB’

8.25 SECURITY

The wordset ‘SECURITY’ contains words that are used by control words to abort with an error message if the control structure is not correct. Some say that this is not Forth-like. You only need to know them if you want to extend the ‘CONTROL’ wordset.

8.25.1 !CSP

Name: !CSP

No stackeffect

Attributes:

Description: Save the stack position in **CSP** . Used as part of the compiler security.

8.25.2 ?COMP

Name: ?COMP

No stackeffect

Attributes:

Description: Issue error message if not compiling.

See also: ‘?ERROR’

8.25.3 ?CSP

Name: ?CSP

No stackeffect

Attributes:

Description: Issue error message if stack position differs from value saved in ‘**CSP**’ .

8.25.4 ?DELIM

Name: ?DELIM

No stackeffect

Attributes:

Description: Parse a character and issue error message if it is not a blank delimiter.

8.25.5 ?EXEC

Name: ?EXEC

No stackeffect

Attributes: FIG,WANT

Description: Issue an error message if not executing.

See also: ‘?ERROR’

8.25.6 ?LOADING

Name: ?LOADING

No stackeffect

Attributes: FIG,WANT

Description: Issue an error message if not loading

See also: '?ERROR'

8.25.7 ?PAIRS

Name: ?PAIRS

Stackeffect: n1 n2 —

Attributes:

Description: Issue an error message if 'n1' does not equal 'n2' . The message indicates that compiled conditionals do not match.

See also: '?ERROR'

8.25.8 ?STACK

Name: ?STACK

No stackeffect

Attributes:

Description: Issue an error message if the stack is out of bounds.

See also: '?ERROR'

8.25.9 CSP

Name: CSP

Stackeffect: — addr

Attributes: U

Description: A user variable temporarily storing the stack pointer position, for compilation error checking.

8.26 STACKS

The wordset 'STACKS' contains words related to the *data stack* and *return stack* . Words can be moved between both stacks. Stacks can be reinitialised and the value used to initialise the *stack pointer* 's can be altered.

8.26.1 .S

Name: .S

Stackeffect: from to —

Attributes:

Description: Print the stack, in the current base. For stack underflow print nothing.

See also: 'LIST'

8.26.2 >R

Name: >R

Stackeffect: n —

Attributes: ISO,FIG,C

Description: Remove a number from the *data stack* and place as the most accessible on the *return stack* . Use should be balanced with R> in the same definition.

See also: ‘R@’

8.26.3 CLS

Name: CLS

Stackeffect: i*x —

Attributes:

Description: Clear the data stack

See also: ‘DSP@’

8.26.4 DEPTH

Name: DEPTH

Stackeffect: — n1

Attributes: ISO

Description: Leave into ‘n1’ the number of items on the data stack, before ‘n1’ was pushed.

See also: ‘DSP@’

8.26.5 DSP!

Name: DSP!

Stackeffect: addr —

Attributes:

Description: Initialize the data stack pointer with ‘addr’ .

See also: ‘DSP@’

8.26.6 DSP@

Name: DSP@

Stackeffect: — addr

Attributes:

Description: Return the address ‘addr’ of the data stack position, as it was before DSP@ was executed.

See also: ‘S0’ ‘DSP!’

8.26.7 R0

Name: R0

Stackeffect: — addr

Attributes: U

Description: A user variable containing the initial location of the return stack.

See also: ‘RSP!’

8.26.8 R>

Name: R>

Stackeffect: — n

Attributes: ISO,FIG

Description: Remove the top value from the *return stack* and leave it on the *data stack* .

See also: ‘>R’ ‘R@’

8.26.9 R@

Name: R@

Stackeffect: — n

Attributes: ISO

Description: Copy the top of the return stack to the data stack.

See also: ‘>R’ ‘<R’

8.26.10 RDROP

Name: RDROP

Stackeffect: —

Attributes:

Description: Remove the top value from the return stack.

See also: ‘>R’ ‘R@’ ‘R>’

8.26.11 RSP!

Name: RSP!

Stackeffect: addr —

Attributes:

Description: Initialize the return stack pointer with ‘**addr**’.

See also: ‘RSP@’

8.26.12 RSP@

Name: RSP@

Stackeffect: — addr

Attributes:

Description: Return the address ‘**addr**’ of the current return stack position, i.e. pointing the current topmost value.

See also: ‘R0’ ‘RSP!’

8.26.13 S0

Name: S0

Stackeffect: — addr

Attributes: U

Description: A user variable that contains the initial value for the data stack pointer.

See also: ‘DSP!’

8.27 STRING

The wordset ‘STRING’ contains words that manipulate strings of characters. In ciforth strings have been given their civil rights. So they are entitled to a *denotation* (the word ") and have a proper fetch and store. An (address length) pair is considered a *string constant* . It may be trimmed, but the data referring to via the address must not be changed. It can be stored in a buffer, a *string variable* , that contains in its first cell the count. Formerly this was in the first byte, and these are called *old fashioned string* ’s (or less flatteringly: brain-damaged).

8.27.1 \$!-BD

Name: \$!-BD

Stackeffect: sc addr —

Attributes: WANT

Description: Store a *string constant* ‘sc’ in the *old fashioned string* variable at address ‘addr’, i.e. it can be fetched with COUNT . (Where would that BD come from?)

See also: ‘COUNT’ ‘\$!’

8.27.2 \$!

Name: \$!

Stackeffect: sc addr —

Attributes:

Description: Store a *string constant* ‘sc’ in the string variable at address ‘addr’.

See also: ‘\$@’ ‘\$+!’ ‘\$C+’

8.27.3 \$+!

Name: \$+!

Stackeffect: sc addr —

Attributes:

Description: Append a *string constant* ‘sc’ to the string variable at address ‘addr’.

See also: ‘\$@’ ‘\$!’ ‘\$C+’

8.27.4 \$,

Name: \$,

Stackeffect: sc — addr

Attributes:

Description: Allocate and store a *string constant* ‘sc’ in the dictionary and leave its address ‘addr’.

See also: ‘\$@’ ‘\$!’

8.27.5 \$/

Name: \$/

Stackeffect: sc c — sc1 sc2

Attributes:

Description: Find the first ‘c’ in the *string constant* ‘sc’ and split it at that address. Return the strings after and before ‘c’ into ‘sc1’ and ‘sc2’ respectively. If the character is not present ‘sc1’ is a null string (its address is zero) and ‘sc2’ is the original string. Both ‘sc1’ and ‘sc2’ may be empty strings (i.e. their count is zero), if ‘c’ is the last or first character in ‘sc’ .

See also: ‘\$~’ ‘CORA’ ‘\$@’

8.27.6 \$@

Name: \$@

Stackeffect: addr — sc

Attributes:

Description: From address ‘addr’ fetch a *string constant* ‘sc’.

See also: ‘\$!’ ‘\$+!’ ‘\$C+’

8.27.7 \$C+

Name: \$C+

Stackeffect: c addr —

Attributes:

Description: Append a char ‘c’ to the string variable at address ‘addr’.

See also: ‘\$@’ ‘\$!’ ‘\$+!’

8.27.8 \$^

Name: \$^

Stackeffect: sc c — addr

Attributes:

Description: Find the first ‘c’ in the *string constant* ‘sc’ and return its ‘addr’ if present. Otherwise return a *nil pointer*. A null string (0 0) or an empty string are allowed, and result in not found.

See also: ‘\$/’ ‘CORA’ ‘\$@’

8.27.9 -TRAILING

Name: -TRAILING

Stackeffect: sc1 — sc2

Attributes: ISO

Description: Trim the *string constant* ‘sc1’ so as not to contain trailing blank space and leave it as ‘sc2’.

See also: ‘?BLANK’

8.27.10 BL

Name: BL

Stackeffect: — c

Attributes: ISO.FIG

Description: A constant that leaves the ASCII value for "blank".

8.27.11 COUNT

Name: COUNT

Stackeffect: addr1 — addr2 n

Attributes: ISO.FIG

Description: Leave the byte address ‘addr2’ and byte count ‘n’ of a message text beginning at address ‘addr1’. It is presumed that the first byte at ‘addr1’ contains the text byte count and the actual text starts with the second byte. Alternatively stated, fetch a *string constant* ‘addr2 n’ from the brain damaged string variable at ‘addr1’.

See also: ‘TYPE’

8.27.12 S"

Name: S"

Stackeffect: — addr1 n

Attributes: ISO

Description: Used in the form: ‘S" cccc’ Leaves an in-line string ‘cccc’ (delimited by the trailing ") as a constant string ‘addr1 n’ . In ciforth the number of characters has no limit and using ‘S"’ has always an effect on HERE , even during interpretation. In ciforth a " can be embedded in a string by doubling it. In non-portable code denotations are recommended.

See also: ‘”’

8.28 SUPERFLUOUS

The wordset ‘SUPERFLUOUS’ contains words that are superfluous, because they are equivalent to small sequences of code. Traditionally one hoped to speed Forth up by coding these words directly.

8.28.1 0

Name: 0

Stackeffect: — 0

Attributes:

Description: Leave the number 0.

See also: ‘CONSTANT’

8.28.2 1+

Name: 1+

Stackeffect: n1 — n2

Attributes: ISO,FIG

Description: This is shorthand for “1 +”.

See also: ‘CELL+’ ‘1-’

8.28.3 1-

Name: 1-

Stackeffect: n1 — n2

Attributes: ISO

Description: This is shorthand for ‘1 -’.

See also: ‘1+ ’

8.28.4 2*

Name: 2*

Stackeffect: n1 — n2

Attributes: ISO

Description: Perform an arithmetical shift left. The bit pattern of ‘n1’ is shifted to the left, with a result identical to ‘1 LSHIFT’. This word should not be used.

See also: ‘2/ ’

8.28.5 2/

Name: 2/

Stackeffect: n1 — n2

Attributes: ISO

Description: Perform an arithmetical shift right. The bit pattern of ‘n1’ is shifted to the right, except that the left most bit (“sign bit”) remains the same. This is the same as ‘S>D 2 FM/MOD NIP’. It is not the same as ‘2 /’ , nor is it the same as ‘1 RSHIFT’.

See also: ‘2*’

8.28.6 Number_1

Name: Number_1

Stackeffect: — 1

Attributes:

Description: Leave the number 1.

See also: ‘CONSTANT’

8.28.7 Number_2

Name: Number_2

Stackeffect: — 2

Attributes:

Description: Leave the number 2.

See also: ‘CONSTANT’

8.29 WORDLISTS

The dictionary is subdivided in non-overlapping subsets: the *word list*’s (see Section 8.6 [DICTIONARY], page 57). They are created by the defining word **NAMESPACE** and filled by defining words while that namespace is **CURRENT** . They regulate how words are found; different vocabularies can have words with the same names.

A word list in the ISO sense has no name, but a *word list identifier* or *WID* , which is inconvenient. We use namespace words created by the defining word **NAMESPACE** . They are used to manipulate the word list’s that are associated with them. So vocabularies are nearly the wordlist ’s of the ISO standard, the primary difference is that they have a name.

8.29.1 ALSO

Name: ALSO

No stackeffect

Attributes: ISO

Description: Duplicate the topmost *WID* in the search order stack. If there were already 16 *WID* ’s, ciforth loses the last one. This is not counting the **ONLY** search order. You seldomly want to use this word, because in ciforth by naming a namespace you add it to the order.

See also: ‘CONTEXT’ ‘NAMESPACE’

8.29.2 ASSEMBLER

Name: ASSEMBLER

No stackeffect

Attributes: WANT,NISO,FIG

Description: The name of the namespace that contains machine code definitions. In ciforth execution it pushes the associated word list to the top of the **CONTEXT** stack. (For ISO-compliance it would replace the top.) **ASSEMBLER** is not immediate. This word makes only sense in combination with the words that belong to it. So it is present in loadable form in the screens file `forth.lab`.

See also: ‘**NAMESPACE**’ ‘**LOAD**’

8.29.3 **CONTEXT**

Name: **CONTEXT**

Stackeffect: — addr

Attributes: FIG,U

Description: The context is the address where the WID is found of the wordlist that is searched first. In ciforth ‘**addr**’ actually points to the *search order*, a row of WID’s ending with the minimum search order WID. The corresponding wordlists are searched in that order for definitions during interpretation. This row of WID’s is allocated in the user variable space allowing for compilation in threads. It may contain up to 16 WID’s in this ciforth, while the ISO Search-Order wordset requires a capacity of at least 8.

See also: ‘**PRESENT**’ ‘**NAMESPACE**’ ‘**CURRENT**’ ‘**USER**’

8.29.4 **CURRENT**

Name: **CURRENT**

Stackeffect: — addr

Attributes: FIG,U

Description: A user variable containing the WID of a namespace to which new words will be added. It is the *compilation word list* in the sense of the ISO standard. The WID has the structure of a *dictionary entry*. This allows to link in a new word between the link field of the WID and the next definition.

See also: ‘**NAMESPACE**’ ‘**CONTEXT**’

8.29.5 **DEFINITIONS**

Name: **DEFINITIONS**

No stackeffect

Attributes: ISO

Description: Used in the form: ‘**cccc DEFINITIONS**’ Make the top most *search order* word list, (context), the compilation word list (current). In the example, executing namespace name ‘**cccc**’ add it to the top of the *search order* and executing **DEFINITIONS** will result in new definitions added to ‘**cccc**’.

See also: ‘**CONTEXT**’ ‘**NAMESPACE**’

8.29.6 **ENVIRONMENT**

Name: **ENVIRONMENT**

No stackeffect

Attributes:

Description: The name of the **ENVIRONMENT** namespace. The associated *word list* contains environment queries. The names of words present in **ENVIRONMENT** are recognized by **ENVIRONMENT?**. This word list is not intended to be used as a **CONTEXT** word list; and only as a **CURRENT** whenever you want to add an environment query.

See also: ‘**NAMESPACE**’

8.29.7 FORTH

Name: FORTH

No stackeffect

Attributes: NISO,FIG

Description: The name of the primary namespace. Execution pushes the FORTH *WID*

to the top of the *search order* . (For ISO-compliance it would replace the top, however the phrase ‘ONLY FORTH’ has the effect required by ISO.) Until additional user *word list* ’s are created, new user definitions become a part of FORTH .

See also: ‘CONTEXT’ ‘NAMESPACE’

8.29.8 LATEST

Name: LATEST

Stackeffect: — addr

Attributes: FIG

Description: Leave the dictionary entry address ‘*addr*’ of the topmost word in the **CURRENT** word list.

See also: ‘NAMESPACE’

8.29.9 ONLY

Name: ONLY

No stackeffect

Attributes: NISO

Description: Set the minimum search order, such that only *denotation* ’s (numbers etc.) can be found plus the word FORTH . By using FORTH one can regain control towards a startup search order.

ONLY is actually a regular **NAMESPACE** . The associated *word list* contains mainly prefix words, that scan denotations and are described in the chapter **DENOTATIONS** . If you want to add a denotation, add it to the ONLY wordlist preferably. This prevents masking regular words with the same prefix.

See also: ‘PREFIX’

8.29.10 PREVIOUS

Name: PREVIOUS

No stackeffect

Attributes: ISO

Description: Pop make testthe topmost *WID* from the search order stack. If empty still the ONLY search order is left.

See also: ‘CONTEXT’ ‘NAMESPACE’

8.29.11 VOC-LINK

Name: VOC-LINK

Stackeffect: — addr

Attributes: U

Description: A user variable containing the *dictionary entry address* address of the word most recently created by **NAMESPACE** . All namespace names are linked by these fields to allow **FORGET** to find all vocabularies.

See also: ‘NAMESPACE’

Glossary Index

This index finds the glossary description of each word.

(Index is nonexistent)

Forth Word Index

This index contains *all* references to a word. Use the glossary index to find the glossary description of each word.

(Index is nonexistent)

Concept Index

Mostly the first reference is where the concept is explained. But sometimes in introductory and tutorial sections an explanation sometimes was considered too distracting.

(Index is nonexistent)

Short Contents

1	Overview	1
2	Gentle introduction	3
3	Rationale & legalese	5
4	Manual	7
5	Assembler	23
6	Errors	27
7	Documentation summary	33
8	Glossary	35
	Glossary Index	115
	Forth Word Index	117
	Concept Index	119

Table of Contents

1	Overview	1
2	Gentle introduction	3
3	Rationale & legalese	5
3.1	Legalese	5
3.2	Rationale	5
3.3	Source	5
3.4	The Generic System this Forth is based on	6
4	Manual	7
4.1	Getting started	7
4.1.1	Hello world!	7
4.1.2	The library	8
4.1.3	Development	9
4.1.4	Finding things out	9
4.2	Configuring	10
4.3	Concepts	10
4.4	Portability	12
4.5	Compatibility with lina64 4.0.x	13
4.6	Saving a new system	14
4.7	Memory organization	14
4.7.1	Boot-up Parameters	15
4.7.2	Installation Dependent Code	15
4.7.3	Machine Code Definitions	15
4.7.4	High-level Standard Definitions	16
4.7.5	User definitions	16
4.7.6	System Tools	16
4.7.7	RAM Workspace	17
4.8	Specific layouts	17
4.8.1	The layout of a dictionary entry	17
4.8.2	Details of memory layout	19
4.8.3	Terminal I/O and vectoring	19
4.9	Libraries and options	20
4.9.1	Options	20
4.9.2	Private libraries	22
4.9.3	Stand alone programs	22
5	Assembler	23
5.1	Introduction	23
5.2	Reliability	24
5.3	Principle of operation	24
5.4	The 8080 assembler	25
5.5	Opcode sheets	25
5.6	Assembler Errors	26

6	Errors	27
6.1	Error philosophy	27
6.2	Common problems	27
6.2.1	Error 11 or 12 caused by lower case	27
6.2.2	Error 8 or only error numbers	27
6.2.3	Error 8 while editing a screen	28
6.2.4	Error -13 while trying I/O	28
6.3	Error explanations	28
7	Documentation summary	33
8	Glossary	35
8.1	BLOCKS	36
8.1.1	#BUFF	36
8.1.2	->	36
8.1.3	?DISK-ERROR	36
8.1.4	B/BUF	37
8.1.5	BLOCK-EXIT	37
8.1.6	BLOCK-FILE	37
8.1.7	BLOCK-HANDLE	37
8.1.8	BLOCK-INIT	37
8.1.9	BLOCK-READ	38
8.1.10	BLOCK-WRITE	38
8.1.11	BLOCK	38
8.1.12	DISK-ERROR	38
8.1.13	EMPTY-BUFFERS	38
8.1.14	UPDATE	39
8.1.15	(BUFFER)	39
8.1.16	+BUF	39
8.1.17	BLOCK-SEEK	39
8.1.18	FLUSH	39
8.1.19	OFFSET	40
8.1.20	_FIRST	40
8.1.21	_LIMIT	40
8.1.22	_PREV	40
8.2	COMPILING	40
8.2.1	DLITERAL	40
8.2.2	LITERAL	41
8.2.3	POSTPONE	41
8.2.4	[COMPILE]	41
8.2.5	LIT	41
8.2.6	SDLITERAL	42
8.3	CONTROL	42
8.3.1	+LOOP	42
8.3.2	?DO	42
8.3.3	AGAIN	43
8.3.4	BEGIN	43
8.3.5	CO	43
8.3.6	DO	43
8.3.7	ELSE	44
8.3.8	EXIT	44
8.3.9	IF	44
8.3.10	I	45

8.3.11	J	45
8.3.12	LEAVE	45
8.3.13	LOOP	45
8.3.14	RECURSE	45
8.3.15	REPEAT	46
8.3.16	SKIP	46
8.3.17	THEN	46
8.3.18	UNLOOP	46
8.3.19	UNTIL	47
8.3.20	WHILE	47
8.3.21	(+LOOP)	47
8.3.22	(;)	47
8.3.23	(?DO)	48
8.3.24	(BACK	48
8.3.25	(DO)	48
8.3.26	(FORWARD	48
8.3.27	0BRANCH	48
8.3.28	BACK)	48
8.3.29	BRANCH	49
8.3.30	FORWARD)	49
8.4	DEFINING	49
8.4.1	;	49
8.4.2	CONSTANT	49
8.4.3	CREATE	50
8.4.4	DATA	50
8.4.5	DOES>	50
8.4.6	MAX-USER	50
8.4.7	NAMESPACE	51
8.4.8	USER	51
8.4.9	VARIABLE	51
8.4.10	WORDLIST	51
8.4.11	colon	52
8.4.12	(;CODE)	52
8.4.13	(CREATE)	52
8.4.14	;CODE	52
8.4.15	HEADER	53
8.4.16	LINK	53
8.5	DENOTATIONS	53
8.5.1	Prefix_"	53
8.5.2	Prefix_&	54
8.5.3	Prefix_+	54
8.5.4	Prefix_-	54
8.5.5	Prefix_0	54
8.5.6	Prefix_7	54
8.5.7	Prefix_B	54
8.5.8	Prefix_TICK	55
8.5.9	Prefix_^	55
8.6	DICTIONARY	55
8.6.1	' (This addition because texinfo won't accept a single quote)	55
8.6.2	,	56
8.6.3	2,	56
8.6.4	>BODY	56
8.6.5	ALLOT	56
8.6.6	BODY>	56

8.6.7	C,	57
8.6.8	DP	57
8.6.9	FIND	57
8.6.10	FORGET	57
8.6.11	FOUND	57
8.6.12	HERE	58
8.6.13	ID	58
8.6.14	IMMEDIATE	58
8.6.15	PAD	58
8.6.16	PREFIX	58
8.6.17	PRESENT	59
8.6.18	WORDS	59
8.6.19	[']	59
8.6.20	(FIND)	59
8.6.21	>CFA	59
8.6.22	>DFA	60
8.6.23	>FFA	60
8.6.24	>LFA	60
8.6.25	>NFA	60
8.6.26	>PHA	60
8.6.27	>SFA	61
8.6.28	>VFA	61
8.6.29	>WID	61
8.6.30	FENCE	61
8.6.31	FOR-VOCS	61
8.6.32	FOR-WORDS	61
8.6.33	FORGET-VOC	62
8.6.34	HIDDEN	62
8.6.35	~MATCH	62
8.7	DOUBLE	62
8.7.1	D+	62
8.7.2	DABS	62
8.7.3	DNEGATE	63
8.7.4	S>D	63
8.8	ENVIRONMENTS	63
8.8.1	CORE	63
8.8.2	CPU	63
8.8.3	ENVIRONMENT?	63
8.8.4	NAME	63
8.8.5	SUPPLIER	64
8.8.6	VERSION	64
8.9	ERRORS	64
8.9.1	?ERROR	64
8.9.2	?ERRUR	64
8.9.3	ABORT"	64
8.9.4	CATCH	65
8.9.5	ERROR	65
8.9.6	ERRSCR	65
8.9.7	MESSAGE	65
8.9.8	THROW	66
8.9.9	WARNING	66
8.9.10	WHERE	66
8.9.11	(ABORT")	66
8.9.12	HANDLER	66

8.10	FILES.....	67
8.10.1	CLOSE-FILE.....	67
8.10.2	CREATE-FILE.....	67
8.10.3	DELETE-FILE.....	67
8.10.4	FILE-POSITION.....	67
8.10.5	GET-FILE.....	67
8.10.6	INCLUDED.....	68
8.10.7	INCLUDE.....	68
8.10.8	OPEN-FILE.....	68
8.10.9	PUT-FILE.....	68
8.10.10	READ-FILE.....	68
8.10.11	REPOSITION-FILE.....	69
8.10.12	WRITE-FILE.....	69
8.10.13	RW-BUFFER.....	69
8.11	FORMATTING.....	69
8.11.1	#>.....	69
8.11.2	#S.....	69
8.11.3	#.....	70
8.11.4	<#.....	70
8.11.5	>NUMBER.....	70
8.11.6	BASE.....	70
8.11.7	DECIMAL.....	70
8.11.8	HEX.....	71
8.11.9	HOLD.....	71
8.11.10	SIGN.....	71
8.11.11	(NUMBER).....	71
8.11.12	DIGIT.....	71
8.11.13	DPL.....	72
8.11.14	ECL.....	72
8.11.15	FLD.....	72
8.11.16	HLD.....	72
8.11.17	NUMBER.....	72
8.12	INITIALISATIONS.....	73
8.12.1	+ORIGIN.....	73
8.12.2	ABORT.....	73
8.12.3	COLD.....	73
8.12.4	DEV-MEM.....	73
8.12.5	INIT.....	73
8.12.6	MMAP-IO.....	74
8.12.7	OK.....	74
8.12.8	OPTIONS.....	74
8.12.9	PERIPHERALS.....	74
8.12.10	QUIT.....	75
8.12.11	VMA-IO.....	75
8.12.12	WARM.....	75
8.13	INPUT.....	75
8.13.1	(ACCEPT).....	75
8.13.2	ACCEPT.....	75
8.13.3	KEY?.....	76
8.13.4	KEY.....	76
8.13.5	PP.....	76
8.13.6	RUBOUT.....	76
8.13.7	TIB.....	76
8.13.8	(>IN).....	77

8.13.9	REFILL-TIB	77
8.13.10	REMAINDER	77
8.13.11	SET-TERM	77
8.13.12	TERMIO	77
8.14	JUGGLING	78
8.14.1	2DROP	78
8.14.2	2DUP	78
8.14.3	2OVER	78
8.14.4	2SWAP	78
8.14.5	?DUP	78
8.14.6	DROP	79
8.14.7	DUP	79
8.14.8	NIP	79
8.14.9	OVER	79
8.14.10	ROT	79
8.14.11	SWAP	79
8.15	LIBRARY	80
8.15.1	L_>IN	80
8.16	LOGIC	80
8.16.1	0<	80
8.16.2	0=	80
8.16.3	<>	80
8.16.4	<	81
8.16.5	=	81
8.16.6	>	81
8.16.7	AND	81
8.16.8	INVERT	81
8.16.9	OR	81
8.16.10	U<	82
8.16.11	XOR	82
8.17	MEMORY	82
8.17.1	!	82
8.17.2	+!	82
8.17.3	2!	82
8.17.4	2@	83
8.17.5	@	83
8.17.6	ALIGNED	83
8.17.7	ALIGN	83
8.17.8	BIC	83
8.17.9	BIS	83
8.17.10	BLANK	84
8.17.11	BM	84
8.17.12	C!	84
8.17.13	C@	84
8.17.14	CELL+	84
8.17.15	CELLS	84
8.17.16	CHAR+	85
8.17.17	CHARS	85
8.17.18	CMOVE	85
8.17.19	CORA	85
8.17.20	EM	85
8.17.21	ERASE	85
8.17.22	FILL	86
8.17.23	L!	86

8.17.24	L@	86
8.17.25	MOVE	86
8.17.26	P!	86
8.17.27	P@	86
8.17.28	PC!	87
8.17.29	PC@	87
8.17.30	PW!	87
8.17.31	PW@	87
8.17.32	TOGGLE	87
8.17.33	WITHIN	87
8.18	MISC	88
8.18.1	.SIGNON	88
8.18.2	EXECUTE	88
8.18.3	NOOP	88
8.18.4	TASK	88
8.18.5	U0	88
8.18.6	-	89
8.19	MULTIPLYING	89
8.19.1	*/MOD	89
8.19.2	*/	89
8.19.3	FM/MOD	89
8.19.4	M*	89
8.19.5	SM/REM	90
8.19.6	UDM/MOD	90
8.19.7	UM*	90
8.19.8	UM/MOD	90
8.20	OPERATINGSYSTEM	90
8.20.1	ARGS	90
8.20.2	BYE	91
8.20.3	EXIT-CODE	91
8.20.4	MS	91
8.20.5	SHELL	91
8.20.6	SYSTEM	91
8.20.7	XOS5	92
8.20.8	XOS7	92
8.20.9	XOS	92
8.20.10	ZEN	92
8.21	OPERATOR	92
8.21.1	*	93
8.21.2	+	93
8.21.3	-	93
8.21.4	/MOD	93
8.21.5	/	93
8.21.6	ABS	93
8.21.7	ARSHIFT	94
8.21.8	LSHIFT	94
8.21.9	MAX	94
8.21.10	MIN	94
8.21.11	MOD	94
8.21.12	NEGATE	94
8.21.13	RSHIFT	95
8.22	OUTPUT	95
8.22.1	(D.R)	95
8.22.2	."	95

8.22.3	.(95
8.22.4	.R	95
8.22.5		96
8.22.6	?	96
8.22.7	CR	96
8.22.8	D.R	96
8.22.9	D.	96
8.22.10	EMIT	96
8.22.11	ETYPE	97
8.22.12	OUT	97
8.22.13	SPACES	97
8.22.14	SPACE	97
8.22.15	TYPE	97
8.22.16	U.	98
8.23	PARSING	98
8.23.1	?BLANK	98
8.23.2	CHAR	98
8.23.3	EVALUATE	98
8.23.4	INTERPRET	98
8.23.5	NAME	99
8.23.6	PARSE	99
8.23.7	PP@@	99
8.23.8	RESTORE-INPUT	99
8.23.9	RESTORE	100
8.23.10	SAVE-INPUT	100
8.23.11	SAVE	100
8.23.12	SET-SRC	100
8.23.13	SOURCE	100
8.23.14	SRC	101
8.23.15	STATE	101
8.23.16	WORD	101
8.23.17	[CHAR]	101
8.23.18	[101
8.23.19	\	102
8.23.20]	102
8.23.21	(102
8.24	SCREEN	102
8.24.1	(LINE)	102
8.24.2	C/L	103
8.24.3	INDEX	103
8.24.4	LIST	103
8.24.5	LOAD	103
8.24.6	LOCK	103
8.24.7	R#	103
8.24.8	SCR	104
8.24.9	THRU	104
8.24.10	TRIAD	104
8.24.11	UNLOCK	104
8.24.12	(BLK)	104
8.24.13	BLK	105
8.25	SECURITY	105
8.25.1	!CSP	105
8.25.2	?COMP	105
8.25.3	?CSP	105

8.25.4	?DELIM	105
8.25.5	?EXEC	105
8.25.6	?LOADING	106
8.25.7	?PAIRS	106
8.25.8	?STACK	106
8.25.9	CSP	106
8.26	STACKS	106
8.26.1	.S	106
8.26.2	>R	107
8.26.3	CLS	107
8.26.4	DEPTH	107
8.26.5	DSP!	107
8.26.6	DSP@	107
8.26.7	R0	107
8.26.8	R>	108
8.26.9	R@	108
8.26.10	RDROP	108
8.26.11	RSP!	108
8.26.12	RSP@	108
8.26.13	S0	108
8.27	STRING	109
8.27.1	\$!-BD	109
8.27.2	\$!	109
8.27.3	\$+!	109
8.27.4	\$,	109
8.27.5	\$/	109
8.27.6	\$@	110
8.27.7	\$C+	110
8.27.8	\$^	110
8.27.9	-TRAILING	110
8.27.10	BL	110
8.27.11	COUNT	110
8.27.12	S"	111
8.28	SUPERFLUOUS	111
8.28.1	0	111
8.28.2	1+	111
8.28.3	1-	111
8.28.4	2*	111
8.28.5	2/	112
8.28.6	Number_1	112
8.28.7	Number_2	112
8.29	WORDLISTS	112
8.29.1	ALSO	112
8.29.2	ASSEMBLER	112
8.29.3	CONTEXT	113
8.29.4	CURRENT	113
8.29.5	DEFINITIONS	113
8.29.6	ENVIRONMENT	113
8.29.7	FORTH	114
8.29.8	LATEST	114
8.29.9	ONLY	114
8.29.10	PREVIOUS	114
8.29.11	VOC-LINK	114

Glossary Index	115
Forth Word Index	117
Concept Index	119